



Photo Editing Software For Snap Lab

User Manual — Exclusively for DNP Printers

June 2017 Version 3.1

1. Contents

1.	Contents	2
2.	License Agreements	5
	Snap Lab Software Licensing Agreement	5
	Ownership Retained By Licensor	5
	Disclaimer of Warranties	5
	Limitation of Liability	5
	Governing Law	6
	Term	6
	Acknowledgments	6
	CC Profiles	6
3.	Introduction	7
	Quick Start	8
	Snap Lab System Setup	8
	Supported Printers	9
	Main panel and Software Management	9
	anguage	9
	Ferms and Conditions	10
	About Print Finishes	11
4.	Loading Images	.12
	How to Load Images?	
	Memory Card	13
	USB Device	13
	iPhone and iPad	14
	Android	16
	Windows Phone 8	17
5.	Event Mode	.19
-	How to Print in Event Mode	19
6	Ordering Products	22
0.	Prints: DS620	.22
	Passnort: DS620	2/
	Biometric Product Information	24
	Passnort All Countries: DS620	27
	rames: DS620	,
	Danaramic Drinte Draduct	20
	Panoramic Prints Floudet	
	Panoramic Print Workflow:	52
	Calendars	
	Single Dage Calendars	
	Multi-Page Calendars (13 Pages Simpley)	
	Collage Product	4 0 ЛЛ
		44
	Tunley Print Products	
	Double Sided Prints	/+/. //7
	Printing Greeting Cards with the DS80DX	+/ /2
	Photobook	
7	Editing Imagos in Kiosk Modo	EC
7.	Eurung Images III NIOSK WOODE	.30 EC
	Luting Jimplex Floudets	

Edit	
Crop	
Effects	
Fine Rotation	
Red Eye	
Text	
Editing Multi-Page Products	
Page commands	
To Add ClipArt:	
Image Editing	
Using Photo Filters	
8. Understanding Order History	
Event Mode Set Up	
9. HOT FOLDER PRINT	
10. Admin Settings – General	
Initial parameters	
Set Up Event Mode	
Print Finish Mode	
Setting the Partial Matte Area	
Screen Saver	
Navigating the Screen Saver Screen	
Creating a New Screen Saver	
Language	
Changing the Language Settings.	
Photo Sources	
Image Editing	
End User Information	
Process Order Confirmation	82
Import/Export Settings	22
Exporting a Configuration File	ده
Exporting a Configuration File	
	04 0E
Supported Passint Printers	۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰۰
Supported Receipt Printers	
Parcodo and OP Codo Sottings	
Order Management System	
Enabling the Order Management System	
Poloacing an Order	
Screen-Shots	
Drinter Deremotors	
Printer Color Adjustments	
Printer Color Adjustments	
Products	
Frint & Frint with Frame	
Single Sided Greating Cards	
Colondar	
Photopoort	101
r ασομοί ί	

Prices	
Frames	
Creating New Frames	
Example of Importing a Frame	
Themes	109
Adding New Themes from Images	
11. Diagnostics	
Team Viewer	112
Printer Status	
Orders in Process	
Receipt Printer Test	
Export Logs	
Software Update	
Updating the Software without an Internect Connection	
12. Statistics	
13. Change Mode: Photo Editing Software vs Party Print	
Change to Party Print Mode	
Launching the Same Mode Again	
Change to Photo Editing Software Mode	
14. Printers configuration support	
System Configurations	
Printer Matrix	
DS820 Printer Support	
Some Key Features:	
DS820 High Quality Media Support	
RX1HS printer support	
15. DNP DS-Printer Firmware Upgrade	
Firmware Upgrade Process - Automatic:	
Firmware Upgrade Process - Manual:	
16. DS620 Printer 6x9 Firmware Update	
17. Troubleshooting	
Contacting Technical Support	
Issue with Wireless Transfer via 'PhotoPrints' App	
Local Immediate Print Product is No Longer Available	

2. License Agreements

Snap Lab Software Licensing Agreement

PLEASE READ THE FOLLOWING TERMS AND CONDITIONS CAREFULLY BEFORE USING THIS SOFTWARE. USING THIS SOFTWARE INDICATES YOUR ACCEPTANCE OF THESE TERMS AND CONDITIONS. IF YOU DO NOT AGREE WITH THESE TERMS AND CONDITIONS, PROMPTLY RETURN THIS SOFTWARE TO YOUR SUPPLIER.

This Software License Agreement is a legal document between you (a single entity) and FIT Engineering S.r.l. (the "Licensor") for the Photo Editing Software (the "Software").

The Software includes the installed software, the associated media, any printed materials, and any electronic documentation. By using the Software, you agree to the terms of this Software License Agreement. The Licensor grants you a non-exclusive, non-transferable license to use one copy of the Software in object code only.

Ownership Retained By Licensor

FIT Engineering S.r.l. owns all title and copyrights in and to the Software and the Licensor has the full right and authority to grant the license granted herein. Your license does not give you any title or ownership in the Software, nor is it a sale of any rights in the Software. The only right granted to you is the right to use the Software in accordance with the terms of this Software License Agreement. All rights not specifically granted to you under this Software License Agreement are reserved by the Licensor.

You may make only a single copy of Software as a backup copy, provided that it includes all notices and markings, including copyright, trademark and other proprietary notices as on the original. Such backup copy of the Software may not be in use at any time unless the original Software is damaged beyond use, and it must remain in your possession and control.

You may not copy the software onto any public network. You may not, and you may not allow others to modify, disassemble, decompile, translate, reverse engineer, reproduce, make derivative works of or enhance the Software. You may not, and you may not allow others to rent, lease, sell, and sublicense or otherwise transfer the Software to any other person.

In addition to any other rights it may have, the Licensor may terminate this Software License Agreement if you fail to comply with the terms and conditions hereof. In such event, you must cease all use of the Software and destroy all copies of the Software and all of its component parts.

At the Licensor's sole discretion, the Licensor may from time to time provide you with updates to the Software. Any such updates shall become part of the Software licensed to you hereunder and subject to all of the terms and conditions of this Software License Agreement.

Disclaimer of Warranties

The Licensor expressly disclaims any and all warranties relative to the Software. THE SOFTWARE IS PROVIDED "AS IS," WITH- OUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR OF PARTICULAR PURPOSE AND NON-INFRINGEMENT AND THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE LICENSED PRODUCT IS WITH YOU.

Limitation of Liability

In no event shall the Licensor be liable for any direct, special, incidental, indirect or consequential damages whatsoever to you including, without limitation, damages for loss of profits, sales or data or for business interruption) arising out of the use of or inability to use the Software, even if the Licensor has been advised of the possibility of such damages. In any event, the Licensor's entire liability under any provision shall be limited

to the amount actually paid by you for the Software. Because some states and jurisdictions do not allow the exclusion or limitation of liability, the above limitation may not apply to you.

If any provision of the Software License Agreement is declared by a court of competent jurisdiction to be invalid for any reason, such invalidity shall not affect the remaining provisions hereof.

Governing Law

This Software License Agreement shall be governed by the laws of Italy without regard to conflict of laws principles.

Term

This License Agreement is effective until terminated. You may terminate this License Agreement by returning the Licensed Product to Licensor. Licensor may terminate this License Agreement if you breach any of the terms and conditions. Upon termination of this License Agreement for any reason, you shall return the Licensed Product to Licensor. All provisions of this Agreement relating to disclaimers of warranties, limitation of liability, remedies, or damages, and Licensor's proprietary rights shall survive termination.

YOU ACKNOWLEDGE YOU HAVE READ AND UNDERSTAND THIS AGREEMENT AND AGREE TO BE BOUND BY ITS TERMS. YOU FURTHER AGREE THAT THIS AGREEMENT IS THE COMPLETE AND EXCLUSIVE STATEMENT OF THE AGREEMENT BETWEEN YOU AND LICENSOR, AND SUPERSEDES ANY PROPOSAL OR PRIOR AGREEMENT, ORAL OR WRITTEN, AND ANY OTHER COMMUNICATIONS RELATING TO THE SOFTWARE ADDRESSED IN THIS AGREEMENT.

Acknowledgments

This document is for informational purposes only. FIT Engineering S.r.l. makes no warranties, expressed or implied, as to the information in this document.

ICC Profiles

Dai Nippon Printing Co., Ltd. (DNP) provided ICC profiles implemented into Photo Editing software.

3. Introduction



Photo Editing Software is a software system to make Prints, Calendars, Prints with Frames of various sizes and Passport photos. The software system allows the selection and editing of digital images to be printed with DNP printer(s) only. When the DS620 printer is connected with the respective media, the product line items will be enabled automatically; this will save the user time in configuring products.

This Photo Editing Software version provides the following new features:

- Automatic firmware upgrade for DS620 & DS820 printer
- Panoramic Prints Product for DS620 (6x14, 6x20) and DS820 (8x18, 8x22, 8x26, 8x32) printers
- Simplex 13 Pages, Yearly Calendar (4x8, 6x8 & 8x12)
- New print finishing surface for DS620/820 printers
 - \circ $\,$ $\,$ For more information, see About Print Finishes on page 11 $\,$
 - Luster (available for both DS620/820)
 - Fine matte (only for DS820)
- DS820 printer support
 - DS820 standard and High-Quality media support
- RX1 HS support
- Order release management system
- New photo filters
 - Cartoon, Retro, Illustration, Sepia, Monochrome, Cool Mono-chrome, Tilt-Shift, Soft filter, Cross filter
- Export / Import configuration
- Panoramic printer support
- Additional languages



• New themes for Calendar/Greeting Card/Photobook products



• Under the **Prints with Frames** product selection, there are New Frames for the following square sizes: 4x4, 5x5, 6x6, and 8x8.



Other improvement items

For assistance or support, contact DNP technical support at dnpsupport@dnp.imgcomm.com

Quick Start

Snap Lab System Setup

Before you start working with the Photo Editing Software, connect and <u>switch on</u> the DS620 printer and the Wi-Fi router (PhotoPrints.) Then, turn on the Snap Lab (push the button rear side of the terminal). The Photo Editing Software will automatically display <u>only</u> products that can be printed with connected printers and loaded media when DS620 printer is connected (please, refer to the installation guide).

If the DS620 printer is not connected, the software will display the following message:

No products available. Please verify that the printers are properly connected to the system.

When the printer is connected to the system, the above message will disappear automatically within a few seconds, and the software will display the available products as per the connected printer.



Supported Printers

With Photo Editing Software you can print directly to DNP printers, without installing any drivers.

Supported DNP printers are DS620, DS80DX, DS80, and DS820.

Once connected to the Snap Lab system, the printer is automatically recognized by the Photo Editing Software.

<u>Color profile</u>: The Photo Editing Software uses the most recent color profiles provided by DNP. You can also enter a color profile by entering settings/printer parameters.

Main panel and Software Management

To access the Main panel, first touch the lower left corner and then the lower right corner of the monitor; you can also connect a keyboard and press the **ESC** key. Once in the Main panel, select your options:

- <u>Settings</u>: Access to the basic configuration of the software, i.e., initial animation, product management, output profiles, system backup and security.
- <u>Orders</u>: Access to the management panel, where customers' digital orders are displayed.
- <u>Diagnostics</u>: Contains tools for system diagnostics, i.e., generating log files, test receipt, check printers.
- <u>Stats</u>: Possibilty to check sales information based on various elements.
- <u>Quit application</u>: Close the software. Use this feature to properly exit from Photo Editing Software.
- <u>In service</u>: Exits the Configuration Panel and returns to initial animation.

Language

The end user can select their native language:





Terms and Conditions

Terms and conditions can be turned ON and OFF. To turn off Terms and Conditions:

1. From the **Admin** screen, click the **Settings** button.

Settings	Pictures	Stats	Diagnostics
Computer reboot	Computer shutdown	Quit application	In service
	() in		

2. Under the General section, click the Intial Parameters button.

General	System	Products
initial parameters	network	printer parameters
mode	automatic shutdown	products
screen saver	import data	prices
language	export data	themes
photo sources	receipt	frames
image editing	printogo	biometric passport
end user informations		
process confirmation		
hot folders		

3. In the Display Terms & Agreements field, select ON or OFF.

DNP Photo Imaging Europe can not be held responsible for any loss of data when using this system. To avoid potential risk of data loss, we recommend you make a backup before using this system. Copyright notice: It is illegal to reproduce photographs taken by a professional photographer or other works subject to copyright without the permission of the copyright holder. If you do not know if the photo you want is protected by copyright, please see our Photo Specialist who will be happy to help you. By reproducing this photograph, recognize that I reproduce the image is not subject to copyright or that I have obtained permission from the copyright holder. We are not responsible for changes in print/film colors that may occur over time and film left over 30 days. Any illegal content may be reported to authorities.
back I Agree I Do Not Agree

Note:

The end user must accept the terms and conditions of the software before the images begin to load. If the end user doesn't agree, the user can simply click the **I Do Not Agree** button, which results in the software displaying the screen saver. The **Terms & Agreement** screen is displayed in the language selected by the end user. If the end user clicks the **Back** button, the Photo Editing Software returns to the **Language Selection** menu.



About Print Finishes

In addition to the Glossy and Matte finishes, there are two (2) new photo finishes available:

- Luster : Available on both DS620 and DS820 printers
- Fine Matte: Available only on DS820 printer

Attention:

The software enables the photo finishes automatically for connected printers.

If any settings have been configured/changed by the operator, then the software won't propose default photo finishes.

• DS620 Printer: the software proposes the following photo finishes:



• DS820 Printer: the software proposes the following photo finishes:



Note:

If DS40/DS80/RX1/RX1-HS/DS80DX are connected, then Luster and Fine Matte are not applicable. The fine matte print finish will be available with the next printer update. Check with your sales representative or customer support for updates on when a new version of Photo Editing Software will be available.



4. Loading Images

The user can upload images to the kiosk from the following devices:

- Memory Card
- USB
- iPhone/iPad
- Android
- Windows Phone
- PhotoPrints Wi-Fi Application
- Social Network

These items can be turned **ON** or **OFF** by following these steps:

1. From the **Admin** screen, click the **Settings** button.



2. Under the **General** section, click the **Photo Sources** button.

General	System	Products
initial parameters	network	printer parameters
mode	automatic shutdown	products
screen saver	import data	prices
language	export data	themes
photo sources	receipt	frames
image editing	printogo	biometric passport
end user informations		
process confirmation		
hot folders		

3. Turn the upload devices **ON** or **OFF** as needed.

How to Load Images?

The user can upload images to the kiosk from the following devices:

- Memory Card
- USB
- iPhone/iPad
- Android
- Windows Phone



- PhotoPrints Wi-Fi Application
- Social Network
- 4. After selecting your product, the **Image Source** screen is displayed.



- 5. Insert your digital media into appropriate port of the Snap Lab Kiosk.
- 6. Select the digital media type from which you want to load images.

Memory Card

1. Insert the memory card in the appropriate port to display all the images stored on the media.



- 2. Select images and press next to load selected images.
- 3. The memory card must be removed to finalize the order.



USB Device

1. Insert the USB stick into the USB port and the software will display images / folders of the media.





- 2. By selecting a folder, images contained in that folder are displayed.
- 3. Select images and press Next to load selected images.
- 4. The USB stick must be removed to finalize the order.



iPhone and iPad

1. After selecting the **iPhone and iPad** option, a selection screen with two possibilities is displayed. You can select **Connection with Cable** or **Wi-Fi**.



2. Wired Connection for iOS:





- 3. If the device is not ready, then the software will make request to you verify your device.
 - Please unlock your mobile device before connecting.
 - Please remove a security access.
 - Please trust this system when a message pop-ups in your mobile device.



4. The cable connection of the mobile device must be removed to finalize the order.



5. Wi-Fi Connection for iOS:

Note:

Wi-FI connection for both <u>iOS & Android</u> requires 'OPhotoPrints' router. Make sure the router is well connected and powered ON. For Wi-Fi connection, the user is prompted to download and install the DNP **PhotoPrints** app for iOS devices.

6. Follow the instructions in the interface to transfer images from the DNP PhotoPrints app.

1. Download the "PhotoPrints" app from the App Store on your Apple device. Scan the QR Code	
2. Connect your Apple device to the 'OPhotoPrints' WiFi network.	
In the 'PhotoPrints' app, select the pictures that you wish to send to the kiosk,	
5, Select your klosk: Klosk ID: K105k 89 Password: 99	
A back A speed A sout	

- 7. When image transfer is completed, the user can see the image thumbnail in the interface.
- 8. Click on Next to place an order.



Android

1. After selecting the **Android** option, a selection screen with two possibilities is displayed. You can select **Connection with Cable** or **Wi-Fi**.



2. Wired Connection for Android:



- 3. If the device is not ready, then the software will make request that you verify your device.
- 4. Please unlock your mobile device before connecting.
- 5. Please remove a security access.
- 6. Please trust this system when a message pop-ups in your mobile device.



7. The cable connection of the mobile device must be removed to finalize the order.





8. Wi-Fi Connection for Android:

Note:

Wi-FI connection for both <u>iOS & Android</u> requires 'OPhotoPrints' router. Make sure the router is well connected and powered ON.

For Wi-Fi connection, the user is prompted to download and install the DNP **PhotoPrints** app for Android devices.

9. Follow the instructions in the interface to transfer images from the DNP **PhotoPrints** app.



- 10. When image transfer is completed, the user can see the image thumbnail in the interface.
- 11. Please click **Next** to place an order.

Windows Phone 8

1. After selecting the **Windows Phone 8** option, you are prompted to connect your phone by a cable. A mobile app is not currently available for Windows Phones.







Note: Only Windows 8 Mobile OS is supported.



5. Event Mode

How to Print in Event Mode

1. Select the desired Language.



- 2. From the Terms & Agreement screen, click the Accept button.
- 3. Click the **Prints** button



- 4. Insert your digital media into appropriate port.
- 5. Select the digital media type from which you want to load images.





Note:

You can select one of the following: Memory Card, USB Device, iPhone or iPad, Android, Windows Phone, or Social Networks.

6. Select the images to be printed.



- 7. Selct the Next button.
- 8. Select Print Finish type.

Note:

Depending on the type of DS-Series printer connected, you can select from Matte, Glossy, Luster, and Fine Matte.

9. When prompted, remove your input device.





10. The system begins printing your image.



6. Ordering Products

Prints, Double Sided Prints, Calendars, Greeting cards and Photobooks can be created with the following workflow procedures.

Prints: DS620

To print a Single Sided Print product:

1. Click the **Prints** button.



2. Select media where images are located, as an example a folder with images.



3. Select images you wish to print. By clicking the + or – buttons, you can add or subtract the amount of prints for each image.



4. Click the **Next** button.



5. Select Product and Paper Finish type.



Note:

Your available options will vary depending on the attached printer loaded media.

6. Click the **Edit** button if you wish to make any edits to your images.



Note:

Please see Editing Images in Kiosk Mode on page 56 to learn more about editing your images.

7. At the Order Summary screen, you can view your current order, add additional products, cancel your order, etc.

	Ord	er summary		
		\oslash		
		(+) ar		
۲) back	🗙 cancel 🏵 n		



- 8. Click the Next button
- 9. Type the **Customer Name**.



10. Click the **Next** button to finish the order.

Passport: DS620

This is the workflow for creating and printing a passport product.

1. Click the **Passport Photos** button to make a passport t product.



2. Click the **Passport Photos** or **All Countries** button.



3. Select the digital media type from which you want to load images.





4. Select images.



5. Select paper finish type.



6. Please wait awhile the system generates the passport product.





- 7. To edit the photo, click the **Edit** button. To change the current photo, click the **Replace Photo** button.
- 8. Click the + or button to increase/decrease the quantity.



Note:

When the quality of the image is low resolution, the system displays a **Low Quality** message, as shown above.

9. At the Order Summary screen, you can view your current order, add additional products, cancel your order, etc.

Order s	ummary	
Product	Quantity	
	1	
	+ add products	
🗲 back 🗙	cancel 🔿 next	

10. Type the Customer Name.



11. Click the **Next** button to finish the order.



Biometric Product Information

Biometric Photo product (**Optional License is required**): Product name and date are printed on the final output.



Passport All Countries: DS620

1. When the **All Countries** button is selected, the software displays a list of available countries.





2. When you select a Country from the column on the left, the available ID products for that country are displayed in the column on the right, as shown below.



Frames: DS620

This is the workflow for creating and printing image with Frames.

1. Click the **Frames** button.



2. Select the digital media type from which you want to load images.



- 3. Select your images.
- 4. By clicking the + or buttons, you can add or subtract the amount of prints for each image.



5. Select product and paper finish type.



6. Choose the desired Frame.







7. Edit the print quantity, crop and enhance images, and add text to your image as necessary.



8. To change to a different frame, click on Graphics tab and select the new frame.



9. At the Order Summary screen, you can view your current order, add additional products, cancel your order, etc.



Order summary		
Product	Quant	
		\bigcirc
	🕂 add	products
🗲 back 🛞 d	cancel 🔿 next	

10. Type the **Customer Name**.

fill in your information
× 1 2 3 4 5 6 7 8 9 0 - = \ 🛠
😔 back 🔕 cancel 🅘 next

11. Click the **Next** button to finish the order.

Panoramic Prints Product

Panoramic prints are great for displaying landscape, wildlife, nature and cityscape photographs. Printing panorama portraits on DNP Dye-Sub technology is an artistic and contemporary representation of your digital photos. Whether it is an amazing landscape, a picture perfect family photo or just something that catches your eye, you can enlarge your photo and we can print it!

	Select the product	
	000	
Prints	Passport photos	Frames
Panoramic prints	Calendars	
	back 🗙 cancel	

Note:

Panoramic prints are available only with DNP DS620 and DS820 printers.

Panoramic prints uses the standard media for both DS620 and DS820 printers, i.e., no special media/paper required.

Panoramic print products are enabled automatically by detecting DS620 and DS820 printers.

Panoramic Print Sizes

The Photo Editing Software provides the following print sizes for the panoramic product:

Print Products : Panoramic		Media/Panel usage	
Panoramic Prints	6x14	DS620 w 6x8 & 6x9 Media	2 panels of 6x8/6x9
Panoramic Prints	6x20	DS620 w 6x8 & 6x9 Media	3 panels of 6x8/6x9
Panoramic Prints	8x18	DS820 w 8x10 & 812 media	2 panels of 8x10/8x12
Panoramic Prints	8x26	DS820 w 8x10 & 812 media	3 panels of 8x10/8x12
Panoramic Prints	8x22	DS820 w 8x12 media only	2 panels of 8x12
Panoramic Prints	8x32	DS820 w 8x12 media only	3 panels of 8x12

Attention:

No other sizes/formats are possible with Panoramic Print products.



Panoramic Print Workflow:

This is the workflow for creating and printing panoramic products.

1. Click the Panoramic Prints button.



2. Select the digital media type from which you want to load images.



3. Select a print size.



4. Select photo finish type.





Note:

If a DS820 printer is connected, then the software enables the sizes for the DS820 printer and its media type automatically.

If both a DS620 and a DS820, then the software enables the possible print sizes automatically of the printer(s) media type.

5. Select an image.



6. If you wish to make any edits to your image, click the **Edit** button and then make the desired edits.



7. Once the edits are completed, click the **Next** button.





8. At the Order Summary screen, you can view your current order, add additional products, cancel your order, etc.

Order summary				
	Product	Quanti		
			\bigcirc	
		🕂 add p	products	
	E back 🗴	cancel 🔿 next		

9. Type the **Customer Name**.



10. Click the Next button to finish the order.







Calendars

Single Page Calendars

The calendar workflow has improved; you can now use one of your own photos as a background, and you can also select from a variety of calendar styles.

Depending on the calendar template you choose, you can select either a one page calendar or a multi-page calendar (either 2 or 13 pages). If you select a multi-page calendar, you must select the minimum number of images as shown in the software.

To print a calendar:

1. Click the **Calendars** button.



2. Select the digital media type from which you want to load images.


DNP

3. Select a print size.



4. Select a paper finish.



5. Select images.



6. Change image sequence, if desired.





7. Select Calendar options: language, country (for national festivities) and starting month. Once you've made your selection(s), click the **Edit** button next to each field.

Language: English	🕜 edit
Holidays: United Kingdom	🖉 edit
Starting month: January 2017	🖉 edit
eback (🗙) cance	el 🏈 next

- 8. Click the **Next** button.
- 9. Select background theme. You may use one of your own images as the background theme. If decide to use one of your own images, the software will pick an image automatically. You can change this background image image during final image preview by selecting **Background**.



10. Select calendar type





11. Select calendar style.



- 12. The **Page Preview** screen is displayed. Make any desired edits.
- 13. It is possible to zoom and center an image by clicking on it.
- 14. It is possible to add text, clipart, change background and shuffle the position of images.



- 15. If you have ordered a multi-page calendar, make your changes on each page.
- 16. Click the **Next** button to finish the order.
- 17. At the Order Summary screen, you can view your current order, add additional products, cancel your order, etc.



Order s	ummary	
Product	Quan	tity
		\oslash
	🕂 add	products
🗲 back 🗙	cancel Э next	

18. Type the **Customer Name**.

					\$10	in y	eur	im	for	me	nio	1						
	ł																	
																0770		
Ĺ	1	2	2 3	4	•	5 6	7	8	8	9	0	-		\square		$\langle X $		
Tet	₹2	Q	W	Ε	R	T	Y	U	Ι	C) P			1	(@		
Cass Lotk	1	1	AS			FG	H		J	к	L	;	÷	treat				
Shit		1	Z	x	С	V	В	N	М			1				ſ		
Symbo	•	2												←	→			
				6	€		\otimes			0	n							

19. Click the **Next** button to finish the order.

Multi-Page Calendars (13 Pages Simplex)

You can now print a **13 Pages Simplex Yearly Calendar**, which is printed with the DS620 or DS820 printer. This **13 pages Simplex Yearly Calendar** can be printed in the following sizes:

- 4x8
- 6x8
- 8x12

To print a 13 Pages Simplex Yearly Calendar:

1. Click the Calendars button.





2. Select the digital media type from which you want to load images.



3. Select print size, in this case **6x8 (13 Pages)**.



4. Select paper finish.





5. Select images.



6. Select a background theme.



7. Change the image sequence, if necessary.





8. Select Calendar options: language, country (for national festivities) and starting month. Once you've made your selection(s), click the **Edit** button next to each field.



9. The **Page Preview** screen is displayed. Make any desired edits.



10. At the Order Summary screen, you can view your current order, add additional products, cancel your order, etc.



Order su	mmary	
Product	Quant	ity
		\checkmark
	🕂 add	oroducts
🗲 back 🗙 ca	ncel 🔿 next	

11. Type the Customer Name.



12. Click the **Next** button to finish the order.

Please wait while printing Calendar 6x8 (13 pages) Luster	

Collage Product

With the Photo Editing Software, you can now print collages, using between two (2) and eight (8) images.

Printing Collages

1. Click the **Collages** button.



2. Select print size and orientation (i.e., horizontal or vertical.)

		Select the pro	duct		-
9x13 H	9x13 V	10x10	10x15 H	10x15 V	
					П
10x20 H	10x20 V	11x15 H	11x15 V	13x13	
13x18 H	13x18 V	13x20 H	13x20 V	13x21 H	

3. Select print finish.



4. Select the digital media type from which you want to load images.





5. Select two (2) to eight (8) images.



- 6. Select background. You can also use one of your own images as a background.
- 7. If ayou use one of your own images as the theme, then the software will select an image automatically.
- 8. You can change the background image during final image preview by selecting **Background**.

	S	elect the them	e:	
Use your photos	Rainbow	Flowers	Black	White
				• * •
Kaleidos	Autumn	Birthday	Christmas	Decorative
Kids	Pets	Spring	Summer	Valentines
	(🕞 back 🗙 canc		

9. The Page Preview screen is displayed. Make any desired edits.





10. By clicking on an image it is possible to zoom and center it.



- 11. It is possible to add text, clipart, change the background, and shuffle the position of images.
- 12. Click the **Next** button to finish the process.

Duplex Print Products

Double Sided Prints



- The workwork flow for double-sided prints is same as the work flow for single-sided printflow.
- Landscape images are folded along the short edge. Portrait images are folded along the long edge.
- Long edge will mean that you turn from one page to the next along the long edge of the paper, much like an A4 magazine or brochure.



Binding Edge: Long Edge

Binding Edge: Short Edge

• Short edge would mean that you turn the page from the short edge of the paper, much like that of a notepad.

Note:

Double Sided Prints are available only with DS80DX printer along with other Duplex Products.

Printing Greeting Cards with the DS80DX

Follow these steps to create and print a Greeting Card.

1. Click the Greeting Cards button.



2. Click the Double-Sided Photo Cards button.





3. Select the digital media type from which you want to load images.



4. Select your images.



5. Select a paper finish.





6. Select a background theme.



7. Change image sequence, if desired.



8. The **Page Preview** screen is displayed. Make any desired edits. See Editing Images in Kiosk Mode on page 56.





9. At the Order Summary screen, you can view your current order, add additional products, cancel your order, etc.

Orde	summary	
	Quantity ouble Sided) Glossy 1	
	(+) add products	
🕞 back 🔕	cancel 🕘 next	

10. Type the **Customer Name**.

					Fill (in y	our	int	tor	nat	ion				
		name													
_															
	` 1	1 2	2 3	4	5	6	7	8	3	9 ()			1	$\langle X \rangle$
	•• ₽ ≜	Q	W	E	R		Y	U	I	0	Ρ	I	1		@
c.	atis Ith	* A	۹ s	D	F	G	H	.	,	(ا		;	1		
		Ŷ	Z	X	c	V	В	Ν	М	,		1			
		ж											+	- -	→ 📖
					ÐÞ		\otimes			0					

11. Click the **Next** button to finish the order.

Note:

Greeting Cards: Are only available if DS80DX printer is connected and Duplex media loaded.

Quantity: The default quantity for 4x8 Greeting Cards is 3 for 8x12 Media. The default quantity for 6x8 Greeting Cards is 2 for 8x12 Media.

Photobook

Follow these steps to create and print a Photobook.





2. Select print size and orientation (i.e., landscape or portrait.)

4x4	4x6 Landscape	4x6 Portrait	8x4 Landscape
6x8 Landscape	8x8	8x10 Landscape	8x12 Landscape
	🕞 back	🗙 cancel	

3. Select the digital media type from which you want to load images.



4. Select your images.





5. Select a background theme.

	Contraction of	
Rainbow	Flowers	Black
White	Kaleidos	
	🕞 back 🛞 cancel	

6. Select a paper finish.



7. Change image sequence, if desired.





8. Type a **Book Title**.

With my friends
` 1 2 3 4 5 6 7 8 9 0 - = \ 🖾
🚾 💤 q w e r t y u i o p [] @
🎬 🔋 a s d f g h j k l ; ' 🚥 🕫
^{2#} ¹ z x c v b n m , . / ^{2#} 1
🕞 back 🛞 cancel 🅣 next

9. Select an image for the cover of your Photobook.



10. The **Page Preview** screen is displayed. Make any desired edits. See Editing Images in Kiosk Mode on page 56.





11. At the Order Summary screen, you can view your current order, add additional products, cancel your order, etc.

O,	der summ	ary	
		\oslash	
		+ add products	
🕞 bacl	k 💌 cancel	() next	

12. Type the **Customer Name**.

fill in your information
<u>`</u> 1234567890-=\
™ # Q W E R T Y U I O P [] @
24 Ê Z X C V B N M , . / 24 Ê
🕞 back 🛞 cancel 🔿 next

13. Click the **Next** button to finish the order.



7. Editing Images in Kiosk Mode

Editing Simplex Products

After loadingyour images, they can be adjusted with multiple tools: crop, effects, fine rotation, and red eye. You can also add text to your images.

Edit

In the workflow, click on the EDIT button control to have the editing options. Other products will present edit page during its workflow.



- Zoom: view images one by one.
- Sort: can be sorted by name or by date.
- **Copies**: select + or buttons to increase or decrease number of copies of selected image.
- Edit: opens the edit page

Crop

Touch and drag on yellow rectangle or use the buttons directly below the selected image to use only a portion of that image.



- **Right** arrow, **Left** arrow, **Up** arrow, **Down** arrow: Move Crop Box, right, left, up or down.
- Zoom: + or -.
- **Rotate**: To rotate the image.
- Fit the Photo: Fit the photo to the selected size, with a white border.
- **Reset**: To reset the changes and revert the image to its original state.

Effects

By clicking on the **AUTO** button the selected image will be automatically adjusted by local density correction.



Auto Color Correction

- Auto: On/Off toggle switch to enable Auto Color Correction for the selected image.
- **Auto All**: On/Off toggle switch to enable Auto Color Correction for the <u>all</u> the images in the directory.
- **Manual**: Enable adjusting the image colors manually.

Fine Rotation

By clicking on the fine rotation buttons, image can be rotated by small angle.



- Straighten
 - Straighten Clockwise
 - Straighten Counter-Clockwise
 - Undo Straighten

Red Eye

1. Click on the + button and wait a moment. If red eye is not automatically corrected, click on the + button again. The maximum correction level is 3.



• Red Eye



- Click on the image to display the **RedEye Control**.
- Select the correction area.
- Click on the + to apply the correction. The maximum times you can press the + button is 3.

Note: By default Auto Red Eye correction is enabled.

Text

Allows you to add text directly to the image, or anywhere on the template.

1. Click on the **Add Text** button.



- 2. Enter the desired text in the textbox.
- 3. In the same dialog box, you can set the the color of the text, font type, font size, etc.



4. Press Enter or the OK button to display the text on the image.



- 5. Select the text to position the text by dragging it, if necessary.
- 6. Select the text for further modification by clicking the yellow **Pencil** icon, if necessary.
- 7. Select the text and click on the Trash Bin icon to delete the text, if necessary.

Editing Multi-Page Products

Page commands

DNP



- **Navigation buttons**: To go to first page, back and forth between pages, and go to last page.
- **Quantity**: To increase and decrease quantity of the product.
- Text: To insert text and insert images.
- **Clipart**: To open the clipart selection window. Select a clipart and click the OK button.
- **Background**: To open the background selection window. You can select a background within the Theme or select an image to be used as background. Background can be applied to current page or to all pages.
- **Shuffle**: To automatically change the layout of current page.
- **Next**: To exit from page editing and proceed to the Order Summary page.

To Add ClipArt:

- 1. Click the **Clip Art** button
- 2. Select the file.



3. Click the **OK** button and the clipart is displayed on the page.





Image Editing



- Edit: Opens the editing window.
- Rotate: To rotate the image inside the box. The image is rotated 90°.
- **Zoom:** To enlarge and decrease image. Change position of image within the layout box.



Using Photo Filters

You can add filters to your images. The following filters are available:

- Monochrome
- Retro
- Sepia
- Tilt-Shift
- Soft-Filter
- Original
- Cool-Monochrome
- Cross-Filter
- Illustration
- Mirror



To access filters, click on the Edit button of any product workflow, and then click on the Filters tab.



8. Understanding Order History

1. From the **Admin** screen, click the **Orders** button.



2. The Orders screen is displayed.

		(Process	Orden export photos	
Number Date	Name	Processed	Product Format		
1. 2000.000		0112.115	Print Lukto		
the 1	r+ ath				
1000 A	range socratige		EDAT-GEOLOGY	No. of the second secon	
				🕞 back 🕐 in service 🏵 next	

- **Process**: A previous order is reprinted. A copy of the order is created.
- **Export photos**: Selected images are exported to a specified folder.
- **Export order**: The selected order is exported to a specified folder.
- **Delete**: The selected order is deleted.
- **Print page**: Select pages are printed.
- **Print until end**: Print all pages from the selected page to last page.

Event Mode Set Up

Event mode is made to help professional and event photographers with a fast and easy way to print images. It is based on the prints workflow, with possibilities to customize almost all functions in order to provide fastest possible service at the event. At beginning of workflow there is no product selection screen. Only prints are available so product selection screen is skipped. It is possible to load images from all media or only from a specific folder. Events mode is an alternate mode to the default "kiosk" mode.



9. HOT FOLDER PRINT

The *Hot Folder Print* function allows instant printing of images as they are dropped (copied) into a folder. There is one folder for each available print size. Folder name is same as related print size.

As an example, to print a 10x15 cm sheet copy an image into folder: "C:\DS-Tmini_DNP Hot Folder\10x15".

The following image types are accepted in this version of Hot Folder Print:

- JPG/JPEG
- TIF/TIFF
- PNG
- BMP
- 3. The hot folders are created automatically according to connected printer under the folder "C:\DS-Tmini_DNP Hot Folder".

This is an example of a system connected to a DS620 printer:



* inch * cm

4. To setup Hot Folder Print, enter Main panel, select Settings and then select Hot Folders.



	Configuration	
initial parameters	network	printer parameters
mode	automatic shutdown	products
screen saver	import data	prices
language	export data	themes
photo sources	receipt	frames
image editing	printogo	biometric passport
end user informations		
process confirmation		
hot folders		
e	back 🕑 in serv	ice

5. The Hot folder settings window will show:

	Confiduration	
	Hot folder	
	Enabled	du
eter	Yes	nte
	Default quantity 1	odu
	Paper type Glossy	ces eme
s	Use default borders NO	me
}	Partial matte Disabled	ome
rm.	Keep the photos in an archive for these days (0 = no archive) $$O$$	
	channels	
	OK Cancel	

- 6. Use the descriptions below to make any necessary changes:
 - **Enabled**: set Yes or No. If set to "No" the hot folder print function will be disabled. All settings will be kept in place.
 - **Default quantity**: set default number of prints for each image copied into each folder.
 - Paper type: set the paper finish to be used by all print sizes
 - Use default borders: set Yes or No. If set to yes, images will be printed combined with PNG graphics set into the print channel.
 - **Partial matte**: select form Diasabled / Matte / Fine Matte / Luster. If set one of the 3 possible finishes, it will perform partial matte finish using the graphic set into the print channel.
 - Keep the photos in an archive for these days: set number of days printed images will be saved into "C:\DS-Tmini_DNP Hot Folder\Archive" folder. If set to 0 (zero) images will not be copied into Archive and will be erased from the hot folder immediately after printing.
 - **Channels**: it will open print output channels window. Print channels and settings are same for all Snap Lab products. Only the button to access the print channels is duplicated.



10. Admin Settings – General

7. Access the Main Panel by touching first the **left** and then the **right** lower corners of the monitor.



8. Click on the **Settings** button.



9. The general settings screen appears.

Initial parameters

General	Products
initial parameters	printer parameters
screen saver	products
language	prices
photo sources	themes
image editing	frames
end user informations	
receipt	
process confirmation	

Auto	No
Card reader model	Product price visualization mode
Atech XM-35U	Defaul
Number of days before order elimination	Cancel the order after this time
10	3 minute
	Display warning when the photos are fille
No	No
System of units	
	Centimeter
VAT Rate	
	22,00 %

- 10. From the Main Panel, press the Settings button.
- 11. From the Configuration screen, select the Initial Parameters option.
- 12. Use the settings below to change your configuration:

DNP

- **Run Mode** Set to **Auto** to run the Snap Lab software automatically when you start the console. **Manual** mode requires operator interaction to start the software (double clicking the software icon).
- **Show Cursor** Set to **No** to hide the system cursor (useful for touch screen devices). Set to **Yes** to show system pointer on the screen (useful for operation with a mouse).
- **Card Reader** Select the appropriate card reader model from the available list.
- Price Visualization Mode Change the price display method as needed. Available options are: no price, maximum price, minimum price, all prices (default option), and first price (price for quantity equal to one).
- Number of Days Before Order Elimination Specifies the number of days until processed orders are deleted from the system.
- Cancel the Order after this Time Number of days until cancelled orders are deleted from the system.
- Fit or Fill Only used for the prints product. If set to Yes, the customer is asked whether they want to have their image cropped to the print size aspect ratio (fill mode) or shrunk to fit the full image on the print area (fit mode). No disables this option.
- **Display Warning after Photos are "Filled"** When set to **Yes**, displays a warning when images are cropped using the Fit or Fill setting explained above.
- **Units** Set the unit of measure for the system metric or inches.
- **VAT Rate** Enter the VAT tax rate for the country if applicable. If the country has no VAT tax, enter a value of 0.
- **Catch Printer Errors** When set to **Yes**, a pop up screen appears if any printer errors occur while the system is in use. If you want to hide any printer errors from the interface, set the value to **No**.



Set Up Event Mode

- 1. Enter the Main Panel by touching bottom left corner and then bottom right corner of the screen.
- 2. Click the **Settings** button.



3. Under the **General** section of the **Configuration** screen, click the **Mode** button.

General	System	Products
initial parameters	network	printer parameters
mode	automatic shutdown	products
screen saver	import data	prices
language	export data	themes
photo sources	receipt	frames
image editing	printogo	biometric passport
end user informations		
process confirmation		
hot folders		

4. Click the **Event** button. Make sure the **Event** mode is selected.





5. Your DS Series printers are set to operate in event mode.

Event mode settings

After setting your system to Event Mode, you can configure certain aspects of your system. You can use the scroll bar to reach all parameters.



Description of each parameter

• Allow all media: set Yes or No. If set to Yes, Photo Editing Software will show media loading screen at beginning of workflow

DNP

- Directory with the event photos: if available, set the folder with images for the event.
- If "Allow all media" is set to "No", at beginning of workflow Photo Editing Software will load all images only from this folder.
- If "Allow all media" is set to "Yes", at beginning of workflow the image source screen is displayed and the folder will be visible along with image sources selection.



- Use Event Photos in the Screen Saver: The initial animation will display random images loaded from the folder set for the event.
- **Default Quantity**: Set default number of prints for each image selected by user.
- Allow Photo Editing: Set Yes or No. If set to No, the photo editing button will not be visible.
- **Product**: Set to **Manual Choice** the Photo Editing Software will prompt user with product selection screen. If a product is selected then this product will be the only one available and user will not be able to choose the product during event workflow.
- **Paper Type**: Set to **Manual Choice** the Photo Editing Software will prompt user with paper finish selection screen. If a finish is selected then this will be the only one available and user will not be able to choose the paper finish during event workflow.
- Use Default Borders: Set Yes or No. If set to Yes, images will be printed combined with PNG graphics set into the print channel.
- **Partial Matte** (For more details, please refer to the partial matte section page 18): Select from Disabled / Matte / Fine Matte / Luster. If set one of the 3 possible finishes, it will perform partial matte finish using the graphic set into the print channel.
- **Photo Sources**: Select **Yes** or **No** for each image souce. This will show or hide the corresponding button on image source screen.



Mode					
		Yes		Yes	
Wi-Fi network name			0Photo l	Prints	
Image Editing	9				
Enable 'effects'	Yes	Enable 'streighten' Yes	Enable texts on ph	^{notos} Yes	
Enable 'auto' correct	^{tion} Yes	Enable 'auto all' correction Yes	Enable manual co	rrections Yes	
Enable 'red eyes'				Yes	
All photos auto enh	ancemei	nt	Disa	abled	
Automatic red eye correction Enabled without preview (faster)					
		channels			
			OK	Car	ncel

- Image Editing: this is a duplicate of settings of kiosk mode. These settings will affect only Event mode.
- **Channels**: By selecting "channels" button it is possible to edit some parameters for each print output.
- As an example, select 15x20 cm / 6x8" and then select "edit" button. The channel settings window will be available.



- **Reset**: Reset button function to reset the Event mode settings to standard kiosk mode as the software default settings.
- The operator or the client needs to go back to Event mode for further configuration of event mode.

DNP

channels reset

- **Default Frame**: it is possible to select a frame from existing Snap Lab library or from any image source. Frames must be instered in pairs: one for horizontal (landscape) printed images and one for vertical (portrait) printed images. A frame is a PNG file with transparency in the area where user image will be displayed.
- Frame must have same aspect ratio of the print channel.



The selected frames will show into channel settings window:





• **Partial Matte**: Similar way of frame settings, it is possible to select partial matte graphic. Partial matte graphics must be selected in pairs: one for horizontal (landscape) images and one for vertical (portrait) images.



A partial matte image is a JPEG file with white background and black graphics. Must have same aspect ratio of selected print channel. In correspondence to black graphic the printer will apply the paper finish selected into Event mode settings.

Print Finish Mode

Partial matte is a new feature of the DNP DS620 and DS820 printers. It is the ability to partially coat a section of a photograph with a matte finish. A single print can have different finishes in different areas. This can be used to highlight specific elements (foreground, background, text, etc.), or allow you to add a logo or brand name in a distinctive manner.

In the photo below, the DNP logo is printed in matte while the rest of the picture retains a glossy finish.



Partial matte can be applied to all products with exception of passport products.

1. To enable partial matte, enter Main panel, go to Settings, and select Mode


General	System	Products
initial parameters	network	printer parameters
mode	automatic shutdown	products
screen saver	import data	prices
language	export data	themes
photo sources	receipt	frames
image editing	printogo	biometric passport
end user informations		
process confirmation		
hot folders		

2. Select Kiosk.

Mode					
Иоde				Kiosk	
Partial matte			Dis	sabled	
Memory card is enabled	Yes	USB is enable		Yes	
Enable iPhone and iPad Yes	Enable Andro			s Phone Yes	
PhotoPrints		Social netwo		Yes	
			0Photc	Prints	
	с	hannels			igvee
			OK	Car	ncel

3. Select **Partial Matte** and the finish you prefer, **Matte** in this example.

Mode		
		Kiosk 🕥
Partial matte	10	Matte
Photo sources	Partial matte	
Memory card is enabled	Disabled	Yes
Enable iPhone and iPad	Matte	ws Phone
PhotoPrints	Luster	Ves
Wi-Fi network name	OK Cancel	oPrints
Image Editing		•
	ОК	Cancel

- 4. With the above setting, a portion of the print will have a matte finish. The rest of the image will hve the default print finish type (in this example, glossy).
- 5. The partial matte finish areas are defined by *print channels*, or graphic overlays which are used to distinguish matte area for each available print size. Graphic overlays must also be configured in pairs one for the portrait (vertical) orientation and one for the landscape (horizontal) orientation.

DNP

- 6. A graphic overlay is a JPEG file with white background and black masked area to define the partial matte placement. When the graphic overlay is used, the printer applies the selected partial matte finish type to the masked area.
- 7. Each graphic overlay used for partial matte finish must have the same aspect ratio as the selected print size.
- 8. The Photo Editing Software provides a sample graphic overlay (DNP logo) for each print size. You can create custom overlays using the same properties and settings as the provided sample overlay.

Setting the Partial Matte Area

- 1. To open the partial matte settings, go to the Main Panel and press the **Settings** button.
- 2. From the Configuration screen, select Mode, Kiosk Mode and then Channels.

	Mode					
	Mode			Kid	osk 🕥	
	Partial matte			Disab	ed	et
mod	Photo sources					
lang	Memory card is enabled	Yes			les	ŀ
	Enable iPhone and iPad Yes	Enable Andro	^{id} Yes	Enable Windows Pho	le les	E
imag	PhotoPrints	Yes	Social networ	ks are enabled	/es	spor
	Wi-Fi network name			0PhotoPri	nts	
	Image Editing	C	nannels) ок	Cancel	

3. The Channels screen opens. Select the print size you want to adjust.

1ode	Channels	
ode	🕢 edit	Kiosk 🕥
irtial matte	11x15	Matte
noto sources	13x13	
emory card is enabled	13x18	
	13x20	Yes
able iPhone and iPad Ye:	13x20 Duplex	ows Phone Yes
notoPrints	15x15	
	15x20	Yes
i-Fi network name	15x20 Duplex	to Deinste
aaa Editina	15x23	
lage culting	15x36 Panorama	
	L15v52 Danorama	
	Close	Cancel



Attention:

You must import graphic overlays for both the horizontal and the vertical print size orientations.

4. Select a finish and orientation option (default/partial matte and horizontal/vertical). In this example, select **Partial Matte (Horizontal)**.



- 5. Choose the graphic overlay you want to use from the listed options.
- 6. If the overlay you want to use is not listed, add new overlays using the **Import Files** (import an individual overlay) or **Import from Folder** (import multiple overlays) options.



7. Repeat the above process for selecting the vertical orientation as well.



8. Once you have selected your overlays, the Channel screen displays your updated selections.



Channel		
Name		15x23
Default horizontal frame	Default ver	tical frame
Partial matte (horizontal)	Partial mat	te (vertical)
DNP		
	ЭК	Cancel

9. Press **OK** to save your changes. The partial matte overlay will now print on any images with that print size.



Screen Saver

Use the Screen Saver section to make changes to the screensaver that is shown when the system is not actively in use.

Navigating the Screen Saver Screen

1. Use the **Up** and **Down** arrow buttons to select the desired screen-saver.

Animation
 Sequence
 Random image from: I:\Photo
 Media: Screensaver french Ecran - No Logo.wmv

- 2. To edit the settings for a screensaver, press the **Edit** button.
- 3. To delete a saved screensaver, press the **Delete** button.
- 4. To export a screen saver to another location, press the **Export** button.



Creating a New Screen Saver

- 1. To open the Screen Saver section, from the Main Panel, select **Settings**.
- 2. From the Configuration screen, select Screen Saver.
- 3. Press the **New** button at the top of the page to start a new screen saver.



- 4. Select a resource option. Enter the folder location for that resource file (or files) and any other parameters such as duration, number of repetitions, title, etc. Any text you add is added to the end of the slideshow or video.
 - Animation: Loads an animated screen saver file.
 - Image: Display a static image as the screen saver.
 - **Random Image**: Displays images from the chosen location in random order.
 - Sequence: Displays images from the chosen location in sequence.
 - Video: Loads a video file to use as the screen saver. (The Snap Lab system is not equipped to handle large video files.)
- 5. As an example adding a new video screen saver is as easy as:
- 6. Select Video from the resource list.

Resource	
Begin date 01/01/1900	End date 31/12/2999
Repetitions 1	Frequence 1
File name	
mess	ages
	Cancel

7. Browse to the video location.

*	Open	×
🛞 🌛 👻 🕆 🍺 > This PC	C → Videos V C	Search Videos 🔎
Organize 🔻 New folder		E - 🔟 🔞
 ☆ Favorites ■ Desktop Downloads 30 Recent places 	No items match	ı your search.
👰 This PC		
🗣 Network		
File name:		File video ✓ Open Cancel

8. Press **Open** to open the video and return to the video resource settings.



9. Change the **Repetitions** and **Frequence** settings to your desired output. Repetitions defines the number of times a video will loop. Frequence defines the frequency the video will play.



10. Click Messages and New to add a text message at the end of the video.



11. Enter your text and press **OK** to continue.





12. Click **Close** to close the message window.



13. You can preview the video or close the window when you finish.

Language

The Photo Editing Software offers the following languages.

Available Languages	
Catalan Spain	Italian
Czech	Japanese
English Canada	Norwegian
English UK	Polish
English US	Portuguese
Dutch Netherlands	Romanian
Finnish	Russian
French France	Spanish Spain
French Canada	Spanish Argentina
German	Spanish Colombia
Greek	Swedish
Hungarian	Ukrainian

Changing the Language Settings.

- 1. From the Main Panel, select the **Settings** button.
- 2. From the Configuration screen, select the Languages option.



General initial pa	Language ^{Administrator language} Inglese / English (EN)	ameters
languag	_{Language} Inglese / English (EN)	
photo so image e	Can select language Yes	
end user	Available languages	
receipt process	Currency, Date & Time Default	
	OK Cancel	

The following settings can be adjusted:

- Administrator Language: Display language for the administrator section of the software. The software must be restarted for the changes to take place.
- Language: Display language for the user interface
- Can Select Language: Allows the user to select from the enabled languages for the user interface.
- **Currency, Date & Time:** Select the default time, date, and currency settings by country. The country's settings will be shown in the interface and on any receipts.

Photo Sources

Use the following settings to define the sources from which images are uploaded to your system.

	Photo sources	
General	Social networks are enabled NO	5
initial para	Favorite directory 1	arameters
language		ŝ
photo sou	Favorite directory 2	
image edit	Favorite directory 3	
end user ir		
receipt	Medium	
process cc	Wi-Fi network name OPhotoPrints	
	OK Cancel	

- Social Networks are Enabled: Allows loading of images from social networks. Yes enables the setting, No disables the setting. Internet connection is required for this feature to work properly.
- **Favorite Directory 1-3**: The system allows you to set up to three pre-configured directories from which users can load images. If a directory is listed, a directory button will be shown on in the user interface.



- Image Quality Verification: This setting will specify a low-level resolution parameter to warn customers of possible image quality issues. The levels are defined as:
 - → High: Warns users for images with a resolution lower than 300 DPI (dots per inch).
 - → Low: Warns users if the image resolution is less than 150 DPI.
- **Wi-Fi Network Name**: Name of the Wi-Fi network that is used with the system. The network name you enter must match the network you have created for use with the system.

Image Editing

The Image Editing section allows you to configure your editing settings.

Image Editir	ng				
Enable 'effects'	Yes	Enable 'streighten	Yes	Enable texts on photo	» Yes
Enable 'auto' correction	Yes	Enable 'auto all' ci	orrection Yes	Enable manual correc	ctions Yes
Enable 'red eyes'		Yes	Automatic red eye Enabled w	e correction ithout preview	w (faster)
				OK	Cancel

- Enable 'Effects': Enables all effects available for images such as black and white and sepia color tones.
- Enable 'Straighten': Allows for fine orientation adjustments to images (small degree rotation).
- Enable Text on Photos: Enables the text-on-image button for use.
- Enable 'Auto' Correction: Enables automatic color correction. This is for individual images.
- Enable 'Auto All' Correction: Displays the button to correct color automatically on all images.
- Enable Manual Correction: Allows for manual color correction to individual images.
- Enable Red Eyes: Displays a button for correcting red eye effect.
- Automatic Red-Eye Correction: Displays a button to correct red eye effect on all images automatically.



End User Information

Gener	End user informations
initial	End user name is required
langu	Yes
photo	No
image	End user phone is required
end u	NO E-mail is required
receip	No
proce	OK Cancel

- End user name is required: Requires the customer name to process the order.
- **Room number is required**: Requires a room number to process the order. This setting is especially helpful in for hotel and cruise ship applications.
- End user phone is required: The user must enter a phone number to process the order.
- **E-mail is required**: Requires an email address to process the order.

Process Order Confirmation

The Process Order Confirmation section allows orders to be released in a variety of ways.

Co	onfirmation w	ith pass	vord	U
	ler unlock code			
			etup	
			etup	
	infirmation (in minutes,		ut) 0	J
				~

- Order Confirmation Mode: allows for the following release options:
 - **No Process confirmation**: Releases an order when it is submitted. By default the system is configured with No Confirmation (automatic process).
 - **Confirmation with Password**: Enter a numeric password to release orders.
 - Confirmation with Keypress: Enter a keyboard number sequence to release the order.
 - **Release by Operator/Manually**: Orders can only be released by an operator using the new order release screen.
 - **Release with Barcode**: Orders are released with a barcode (requires barcode scanner and receipt printer).





- **Requires Confirmation for Total Above**: Threshold for requiring a release restriction by monetary amount. Enter the amount to trigger the password confirmation. Orders equal or above this amount prompt for password, orders below this amount are printed without password.
- **Print Receipt**: If enabled, an order receipt is printed for the user. This is useful with order release to show the cashier how much needs to be paid before the order can be released.
- **Print Receipt with Order Unlocks Code**: If enabled, prints the order receipt including the unlock code. Use this option when you have a network receipt printer located close to the cash register so the customer can pay for the order and then receive the unlock code. The unlock code is thenentered at terminal to print the order. The printed unlock code is unique for each order.
- **Printer to use for Unlocks Code Receipt**: click on the button to setup the printer for receipt with unlock code. It could be useful to setup a network printer positioned close to cash register.
- **Custom Text for Confirmation View**: enter the text to show to users which will replace default text on password request screen.
- **Timeout for Order Confirmation**: if set to 0 (zero) there will be no timeout, otherwise kiosk will go to welcome screen after set minutes of inactivity on password entering screen. The order will be deleted.

Import/Export Settings

You can apply a system configurations across multiple consoles.

Exporting a Configuration File

- 1. Open the Main Panel and select the Settings button.
- 2. From the Configuation page, select **Export Data**.
- 3. When the Save As box appears, select where you want to save your configuration file.
- 4. Click Save to save the file.
- 5. It will take a few minutes for the configuration file to save. A please wait message is shown during the saving process.
- 6. When the system returns to the Configuration page, the export is complete.





- 7. A few notes about the exported data:
 - Only available with the Snap Lab system.
 - The export process saves off all configuration data to the system.

DNP

- The process can take up to 10 minutes.
- If the save location is a portable drive (USB or SD), then the process can take longer.
- If frames and templates are included in your system configuration, the process can take longer.

Importing a Configuration File

- 1. Open the Main Panel and select the **Settings** button.
- 2. From the Configuation page, select Import Data.
- 3. When the Open box appears, select the location where your configuration file is saved.
- 4. Click **Open** to begin the configuration.
- 5. The configuration file is imported and applied to the system. This may take up to ten minutes. A "Please wait" message is displayed while the update is applied.
- 6. Once the update is done, you are returned to the Configuration page.

stem Desktop Downloads Downloa		Croanize Vew folder	
xport data	ystem import data	Desktop # Name Downloads # Downlo	Date modified Type 01/10/2016 00:53 Shortcut 01/10/2016 00:53 Compressed (
File name: Backup_2016_10_20 V *.zip V	xport data	S + Oct CneDrive This PC Network File name: Beckup_2016,10,20	v ▼ *±p v



- 7. A few notes about the imported data:
 - Only available with the Snap Lab system.
 - The import process applies all configuration data to the system.
 - The process can take up to 10 minutes.
 - If the save location is a portable drive (USB or SD), then the process can take longer.
 - If frames and templates are included in your system configuration, the process can take longer.
 - Biometric data settings and licensing cannot be applied to other systems.

Receipt

With this setting it is possible to setup an optional receipt printer to release a printed receipt after submitting an order. Before configuring the receipt printer settings, receipt printer driver must be installed on the operating system.

Receipt		
	DP-DS620	
Receipt height	10	
Prints the receipt for the customer NO	Prints the receipt for the shop NO	
Language used for the receipt	nglese / English (EN)	
Title	DS-Tmini	
Line 1		
Line 2		
Footer		
Save a receipt file for each order in	this directory	
Print the ticket on this channel	10x15 on Dnp	
	OKCa	ncel

- **Receipt**: Select your receipt printer from list of installed printers.
- **Receipt Height**: Fixed value for DS620 printer receipt.
- Print the Receipt for the Customer: If enabled a receipt is printed at the end of each order.
- Print the Receipt for the Shop: If enabled, a second receipt is printed for the shop assistant.
- Language: Selects the language used on the receipt print from a list of available languages.
- Title: Title field for the receipt. Can be customized for different events or stores.
- Line 1 and 2: Optional text fields that appear under the title field on the receipt.
- **Footer**: Text printed at the end of every receipt.
- Save a Receipt File: Select a directory to save copies of each receipt file.

Supported Receipt Printers

• *DS620* as receipt printer, the printer driver is already installed.

- While using a DS620 as receipt printer, the supported print formats are 6x8 media (4x6 (10x15) & 6x8 (15x20) print sizes) and 5x7 media (5x7 (13x18 cm)).
- EPSON TM-T20 USB as receipt printer, the printer driver is already installed.
 - \circ $\;$ The device must be connected & configured to release the receipt printer.

NOTE:

The system can accept other types of receipt printers provided the printer driver is installed. The receipt printers must be configured in the system. The Photo Editing Software cannot release a receipt print if the receipt printer is not configured properly.

Configuring the Receipt Printer

- 1. Open the Receipt printer options.
- 2. From the the Receipt Printer field, select the receipt printer you want to use.
- 3. Locate the Print the Ticket on the Channel option and select the desired **print size**.

If you are using a *DS620 printer*, select the **desired print size** for the type of print media loaded. If you are using the *Epson TM-T20 USB* receipt printer, select **NONE** for the print size option.

	DP-DS620	
	10	
	Inglese / English (EN)	
rint the ticket on this channel		

Receipt	Receipt
Prints the receipt for the customer Ves No	Pri Print the ticket on this channel
Language used for the receipt Inglese / English (EN)	Inone 10×10
Title DS-Tmini	Tit 10x10 Duplex
Line 1	Lin 10x15 10x15 Duplex
Line 2	Lin 10x20
Footer	For 10x20 Duplex 11x15
Save a receipt file for each order in this directory	5° 13x13
Print the ticket on this channel	Pri OK Cancel
OK Cancel	OKCance

4. Click on **OK** to save your changes.

Note:

If you are using a DS620 printer for your receipts and you want to turn off receipt printing, follow the above steps and press the **NONE** button to remove the DS620 as the printer.

Barcode and QR Code Settings

Use the following section to add barcodes or QR codes to your receipt.

Adding a Barcode for Each Product

On the receipt ticket it is possible to print a barcode for each product. This will allow faster and more reliable pricing and payment at cash register. The barcode with the related product code will be printed on selected receipt ticket printer in the EAN 13 format. There are two steps to setting up barcode printing: enter the EAN code for each product and enable barcode printing in receipt settings.

1. To enter EAN codes, enter the Configuration screen, then select **Products**.





General	System	Products
initial parameters	network	printer parameters
mode	automatic shutdown	products
screen saver	import data	prices
language	export data	themes
photo sources	receipt	frames
image editing	printogo	biometric passport
end user informations		
process confirmation		
hot folders		

2. Select a product, as an example print 10x15, and select **Edit**.

	🕂 new 🐼 edit	
Passport photo	9x13	(
International passport photo		
	10x10 Double Sided	
Collage	10 15	
	10x15 Double Sided	
Print	10x20	
Single sided photo card	10x20 Double Sided	
Print with frame	11x15	(
Colondor		

3. Select the EAN code field and enter the 12 digit EAN code for that product. Please note that Photo Editing Software will accept only 12 digits numeric code.Press **OK** to save your changes. Press **OK** again to save your product changes.

	- Control Report Processor	
Product	Prod Ean code	
Visible	123456789012	
Yes	Passed 1 2 3 4 5 6 7 8 9 0 - = \ 🖾	
Paper type Icon	Gift ■ ≠ q w e r t y u i o p [] @	
Manual choice	Collag 🚾 🗈 a s d f g h j k l ; ' 🖙 🚽	
Ean code	Prost ====================================	
	Print v Since % ← → □□□	J
OK Cancel	OK Cancel	
	🕒 🖉 back 🕑 in service	

4. To enable barcode printing, open the Configuration screen and select **Receipt**.



General	System	Products
initial parameters	network	printer parameters
mode	automatic shutdown	products
screen saver	import data	prices
language	export data	themes
photo sources	receipt	frames
image editing	printogo	biometric passport
end user informations		
process confirmation		
hot folders		

5. Scroll down to the Print EAN code and set to **YES**.

r	eceipt		
L	ine 1		
L			r
F			
L			ľ
	rint EAN codes Yes		
Р	rint QR code No		
c S	ave a receipt file for each order in this directory		
P	rint the ticket on this channel <undefined></undefined>		
	OKCa	ncel	

6. If a product has an EAN code then this code will be printed on the ticket. There will be one barcode for each product line in an order.

DNP

Adding a Barcode to Release the Order

Attention:

To use this feature, you must have an additional barcode reader device and a receipt printer.

In addition to releasing orders with a password or by an operator, you can also release orders using a barcode.

1. To enable barcode release, enter the Configuration page and select **Process Confirmation**.

General	System	Products
initial parameters	network	printer parameters
mode	automatic shutdown	products
screen saver	import data	prices
language	export data	themes
photo sources	receipt	frames
image editing	printogo	biometric passport
end user informations		
process confirmation		
hot folders		

2. Select the Order Confirmation Mode field.

Process confirmation				
Order confirmation mode Release by barcode				
Confirmation password				
Printer to use for unlock code receipt				
Setup Custom text for confirmation view				
Setup				
OK Cancel				

3. From the list, select **Release by Barcode**.

General initial param mode screen saver	Order confirmation mode This property allows you to use a release mode, so that you confirm every order to continue with printing.	nts parameters cts			
language photo source image editin end user info	No confirmation (automatic process) Confirmation with password Confirmation with keypress Release by operator / manually Release by barcode	s s tric passport			
process conf hot folders	OK Cancel				

DS-Tmini SI

TEST ARTS

= 6 =

- DNP
- 4. Use the following information to update the rest of the settings.
 - **Confirmation Password**: Sets a 4 digit numeric password for operators to release the order. This is available incase the barcode scanner malfunctions.
 - **Printer to use for Unlock Code Receipt**: Select the receipt printer where the barcode will be printed. It is best to have the barcode printer behind a counter or near the cash register. The customer is given the barcode to release the order once it has been paid in full.
 - **Custom Text for Confirmation View**: Enter any special text here that will print on the barcode receipt.

Adding a QR Code to the Receipt

You can have a QR code print on each receipt. This will allow automatic reading of order details.

- 1. QR code information is written in CSV format (comma separated values). At end of a product information section, there is a double comma (,,) which is read byt the software as "start a new line".
- 2. Each product should be entered as: PRODUCT, EAN CODE, SIZE, FINISH, QUANTITY, VAT, PRICE,,
- 3. After all your product lines have been entered, the last two items are the **fix amount** and the **total price** for the order.
- 4. To enable QR code printing on receipt prints, open the Configuration page and select **Receipt**.

General	System	Products
initial parameters	network	printer parameters
mode	automatic shutdown	products
screen saver	import data	prices
language	export data	themes
photo sources	receipt	frames
image editing	printogo	biometric passport
end user informations		
process confirmation		
hot folders		

5. Locate the **Print QR Code** line and set the value to **Yes**.



receipt Lire 1	
Line 2	\square
Footer	
Logo	
Print EAN codes	
rint QR code Yes	
Save a receipt file for each order in this directory	
Print the ticket on this channel <undefined></undefined>	
ОКСа	ncel

Order Management System

The PES system now offers an order management system to manage several orders simultaneously. By enabling this feature, the software can stack multiple orders and allow the operator to decide when an order should be processed using a print processing screen.

Enabling the Order Management System

- 1. Go to the Main Panel and press the **Settings** button.
- 2. From the Configuration screen, select the **Process Confirmation** option.

		Products		
initial parameters	network	printer parameters		
mode	automatic shutdown	products		
screen saver	import data	prices		
language	export data	themes		
photo sources	receipt	frames		
image editing	printogo	biometric passport		
end user informations				
process confirmation				
hot folders				
back 🕑 in service				

3. Click the Order Confirmation Mode field.



4. Select the Release by Operator / manually option. Press OK.

DNP



5. In the Confirmation Password field, enter the new password. The default system password is **0000**. If no new password is entered, the default password will be used. Press **OK** when you are done.

Confirmation password	
4004	

6. In the custom text field, enter any text you want the customer to see when trying to release an order. In this example, "Please contact the operator to release your order" is used. Press the **OK** button to save your custom text.

If you define a customized text here, it is displayed to the user instead of the standard text in the order confirmation view. You can put more information about the confirmation process or some help to the users.

Please contact the operator to release your order

Custom text for confirmation view

Releasing an Order

Let's imagine an order with "Print" products is in the process and the name is given as "Test"

- 1. Depending on your system configuration, a receipt can be printed for orders that need to be release.
- 2. To configure your receipt settings, see "" on page 96.
- 3. Once the screen saver is shown, tap the left and then the right top corners of the screen in sequence.
- 4. Enter the admin password and click **OK**.
- 5. If you enter the wrong password, repeat the above steps with the correct password.
- 6. When the Order Management screen is shown, find the order you want to release.
- 7. Click on the order you want to release. You can only release one order at a time.
- 8. Click **OK** to release the order.
- 9. The system displays waiting and in progress messages as the order is processed and printed.
- 10. If you need to stop the order processing, press the **Cancel** button.

Attention:

If a print job is already in the printer buffer, then the job cannot be cancelled. Only prints that have not been added to the printer buffer can be cancelled. It is normal for up to four prints to print after you press the Cancel button, depending on the order information and printer buffer size.

Screen-Shots:

	Fill	n your inforr	mation		
	name TEST				
		Please wait.			
F	Please contact t	he operator to	o release your c	order	
1	Se	ect your lan	guage	2 Tap on side	the left & right
English	English	English	Français	Français	
passwor #### Er	d 2 2 4 5	ect your land	guage	Enter Pass	sword : 4004
Tab ₹2 (Caps ♀ Lock ♀ Shift Symbols ♀€	2 3 4 3 q w e r a s d f î z x c	tyui ghj vbnm	9 0 2 2 0 p [] k I ; ' , . / smit		
C.	(🗲 back 🛞 c	Ok ancel	Cancel	



Number Date Name Format 9 18/10/2016 08:11:11 TEST 4x6	Orders process (m) delete Software displays the order(s) list	
	🗲 back 🗙 cancel	
Number Date Name Format 9 18/10/2016 08:11:11 TEST 4x6	Orders process de et Select the ord « Test » Click on ' Proc button	ler cess '
Bmb3.jpg	🕞 back 💌 cancel	
Are you s	ure you want process the selected items? OK Cancel	Click on 'Ok' to confirm the order
	Please wait	Please wait







Printer Parameters

			Output profil
General	Products		Resolution 300 x 300 d
initial parameters	printer parameters		Can split orders on many print
language	products		RX1 custom color profile
image editing	themes		DS40 custom color profile
end user informations	frames	i i	DS620 custom color profile
receipt			
process confirmation			DS80 custom color profile
			DS80DX custom color profile
			OK Cano

- Resolution: Option to choose 300x300 dpi or High Quality printing 300x600 dpi.
- Can split orders on many printers: if set to "yes" one order will be sent to all printers able to process that order (an order of 20 prints 4x6 with two DS620 connected and 6x8 media loaded will be split 10 images per printer).
- Custom color profile: it specifies a color profile to be used by each printer model. If no profile is set then default profile is used.

Printer Color Adjustments

In addition to color adjustments to images during the order process, you can also set up color profiles for specific printers and paper finishes.

1. To set the color adjustments for each printer and paper finish, open the Configuration page and select the **Printer Parameters** option.



2. When the Output Profile screen opens, select **Color Corrections per Printer**.



Output profile			
Resolution	300 x 30	0 dpi	
Can split orders on many printers			
RX1 custom color profile RX1V	VHITEUP-P	IE.icc	
DS40 custom color profile			
DS620 custom color profile			
DS80 custom color profile			
DS80DX custom color profile			
channels color co	rrections	per pi	rinter
	OK	Car	ncel

3. When the selection list appears, select **your printer type and paper finish type** from the list. Each printer will have multiple entries – one for each paper finish. If you have multiple printers, select the one with the correct serial number.

Color corrections per printer
🖉 edit
Matte HighDensitySpeed
DS820 (CS6070096) Luster HighDensitySpeed
DS820 (CS6070096) Fine Matte
DS820 (CS6070096) Luster
DS820 (CS6070096) Fine Matte HighDensitySpeed
DS820 (CS6070096) Matte
DS820 (CS6070096) Glossy
[S820 (CS6070096) Glossy HighDensitySpeed
I S620 (DS6X55004409) Glossy
DS620 (DS6X55004409) Luster
DS620 (DS6X55004409) Matte
Close

4. Press the Edit button. The Color Corrections for Specific Printers box will appear.



Color corrections for specific printers						
Model	Serial n DS620	umber	DS6X55004409			
Paper type High Density pr Glossy	nt on supported printers		False			
Apply this color correction			No			
Color profile						
Auto color NO	Auto contrast	No	Auto levels NO			
Brightness (from -100 to 100) O	Contrast (from -100 to	100) O	Saturation (from -100 to 100) O			
Red (from -100 to 100) 0	Green (from -100 to 10)) 0	Blue (from -100 to 100) O			
Gamma (from -100 to 100)	Sharpe O	n (from	n -100 to 100) O			
			OK Ca	ncel		

Description of the screen settings:

- **High Density Mode on Supported Printers**: If set to True, high density mode is used when printing (currently available for DS820 printers only).
- Apply This Color Correction: If enabled, color correction is applied to anything printed using this printer and this color profile.
- **Color Profile**: Opens a browse window so you can select your preferred color profile for this printer and this finish type.
- Auto Color: Automatically correct color and density for prints used with this printer and finish type.
- Auto Contrast: Automatically corrects contrast for images printed with this printer and finish type.
- Auto Levels: Autmatically corrects color levels in images printed with this printer and finish type.
- **Brightness, Contrast, Saturation, Red, Green, Blue, Gamma, Sharpen Controls**: Adjust each channel as needed to make fine adjustments to the printer channel outputs. Set the value to 0 if no correction needs to be applied.

Panoramic Printer:

When two printers of DS 620 or DS 820 are connected with Snap Lab system, the PES provides the possibility to assign a "Panoramic Printer" where panoramic prints printed on the assigned printer.

How to assign a "Pano Printer"?

- 1. Ensure that the system has been connected with two (2) printers, a DS620 and/or a DS820.
- 2. The printers must be turned ON.
- 3. From the Admin screen, click the **Settings** button.
- 4. Under the Products section, select **Printer Parameters**.



Configuration			
		Products	
initial parameters	import data	pr ter parameters	
network	export data	products	
screen saver		prices	
language		themes	
photo sources		frames	
image editing			
end user informations			
receipt			
process confirmation			

5. In the Output Profile dialog box, select **Print Panorama Prints on These Printers**.

	Output profile D5620 custom color profile	
General		cts
initial parame	DS80 custom color profile	
network	DS80DX custom color profile	
screen saver		
language	DS820 custom color profile	
photo source	DS820 custom color profile (Pure Premium)	
image editing	High Density print on supported printers	
end user info	No	
receipt	Print panorama prints only on these printers	
process confi		
	OK Cancel	

6. Select the printer which is going to handle panoramic prints when that product type is selected.

Print panorama prints only on these printers	Print panorama prints only on these printers
select all none	select all none
DS620 (6x8) / DS6X55004409	DS620 (6x8) / DS6X55004409
DS620 (6x8) / DS6X54003570	DS620 (6x8) / DS6X54003570
OKCancel	OKCancel
Print panorama prints only on these printers	Print panorama prints only on these printers
select all none	select all none
DS820 (8x12) / CS6070107	DS820 (8x12) / CS6070107

OK Cancel

DS820 (8x12) / CS6070096

OK

Cancel

Only one panoramic printer can be assigned for a DS620 or DS820.

Attention:

DNP

The software displays the panoramic printer serial-number and its media type for selection purpose.

The software will display a warning message when there are an insufficient number of panels for Panoramic print(s).

When there are no panoramic prints in an order, both the DS620 and the DS820 are used to fullfil the submitted order.

Products

Use this section to add or remove products from the system.

- 7. From the Configuration page, select the **Products** button.
- 8. Click the **Edit** button.
- 9. Enter any necessary details or parameters.
- 10. Press **OK** to save your changes.

Print & Print with Frame

- Enable or disable print sizes as necessary.
- Print sizes are shown based on the printer attached and the media size loaded.
- Print finish types by default have a finish type of manual so the customer can select from a list of available finish types.



Single Sided Greeting Cards

- Only available for DS80DX printers with duplex (double-sided) media loaded.
- You can enable this option for each print size in the category.
- The print sizes are available based on which printer is connected to the system.
- Print finish types by default have a finish type of manual so the customer can select from a list of available finish types.
- The default quantity for 4x8 prints is 3. The default quantity for 6x8 prints is 2. This is set as such to utilize 100% of the 8x12 ribbon panel.
- The incremental & default quantity variable is always equal.
- **Top, Bottom, Left and Right Margins**: Enter the minimum distance in millimeters from the print border to image edge. This setting can be useful to portions of the image being trimmed off when the paper is cut.
- Framing Adaptation: Fit to Layout images are cropped to fit to preset layout. Fit to Image images maintain the original aspect ratio and are not cropped.

Double Sided Greeting Cards

- Only available for DS80DX printers with duplex (double-sided) media loaded.
- You can enable this option for each print size in the category.
- The print sizes are available based on which printer is connected to the system.
- Print finish types by default have a finish type of manual so the customer can select from a list of available finish types.
- The default quantity for 4x8 prints is 3. The default quantity for 6x8 prints is 2. This is set as such to utilize 100% of the 8x12 ribbon panel.
- The incremental & default quantity variable is always equal.

DNP

- **Top, Bottom, Left and Right Margins**: Enter the minimum distance in millimeters from the print border to image edge. This setting can be useful to portions of the image being trimmed off when the paper is cut.
- Framing Adaptation: Fit to Layout images are cropped to fit to preset layout. Fit to Image images maintain the original aspect ratio and are not cropped.

Calendar

- Only available for DS80DX printers with duplex (double-sided) media loaded.
- You can enable this option for each print size in the category.
- The print sizes are available based on which printer is connected to the system.
- Print finish types by default have a finish type of manual so the customer can select from a list of available finish types.
- The default quantity for 4x8 prints is 3. The default quantity for 6x8 prints is 2. This is set as such to utilize 100% of the 8x12 ribbon panel.
- The incremental & default quantity variable is always equal.
- **Top, Bottom, Left and Right Margins**: Enter the minimum distance in millimeters from the print border to image edge. This setting can be useful to portions of the image being trimmed off when the paper is cut.
- Framing Adaptation: Fit to Layout images are cropped to fit to preset layout. Fit to Image images maintain the original aspect ratio and are not cropped.

Photobook

- You can enable this option for each print size in the category.
- Assign the minimum and maximum number of pages, or sheets, per product.
- If the minimum and maximum page counts are equal, then the front side is used for the cover page, and the other pages are filled with images.
- If the number of pages is based on a page range, then number of pages in each order is based on the number of images loaded.
- Select by User: User is prompted to select the number of pages.
- Print finish types by default have a finish type of manual so the customer can select from a list of available finish types.
- A maximum of nine (9) images can be loaded on each page of the layout spread.
- The user can change the framing t
- **Top, Bottom, Left and Right Margins**: Enter the minimum distance in millimeters from the print border to image edge. This setting can be useful to portions of the image being trimmed off when the paper is cut.
- Framing Adaptation: Fit to Layout images are cropped to fit to preset layout. Fit to Image images maintain the original aspect ratio and are not cropped.

Passport

- The operator can configure the passport settings by selecting passport photos and clicking on the **Edit** button.
- By default the software is configured with the individual image size of 45x35mm and 6 copies in a 4x6 print format. There is 2mm of spacing between each image.
- The operator can change all of the values for the print sizing by pressing the **Passport Parameters** button.



- Any product visibility can be changed to ON/OFF
- Once a new product is added, it can't be deleted but it can be turned off from the visible section
- All Countries: How to add more products under 'All Countries'
- Refer the above page & follow the same instructions
- New Passport Product creation displays the metric sizes as per the initial system metrics i.e. Settings/Initial Parameters/System of Units/centimeters or Inches:



Note:

All values must be entered in mm measurments.

Adding a Passport Photo Product

11. Click **New** to add a new product.

Products	
	🕂 new 🕢 edit
Passport photo	Passport photos

- 12. Select Passport Photo or International Passport Photo from the product list.
 - Product
 Passport photo
 International passport photo
 OK Cancel
- 13. Enter a product name. For example: Passport Photo_France
- 14. Enter each value carefully.



	Product						
Products	Name F	asspo	rt Pho	to_FRA	NCE		
	Channel		10	x15 on	Dnp		
Passport photo International passport photo	Visible				Yes		
	Paper type		Ма	nual ch	oice		
	Orientation Horizontal	Rows		Columns			
	Height (in mm)	45.00	Width (in	^{. mm)}	5.00		
	Horizontal spacing	(in mm) 2,00	Vertical s	pacing (in m	^{nm)} 2,00		
	Print cut helpers	snoi	rt nai	rame	tors	\mathbf{igvee}	
				K	Car	ncel	
					Cui		

15. To enter the configuration for each image on the passport photo, press the Passport Parameters button. Be sure to correctly enter each value.

Passport paramete	ers		L	Ability to change from
Face representation	-	Oval		Oval to Rectangle
Min face height (in mm)		32,ŪŪ	_	Min face Height in mm
Max face height (in mm, 0 = auto)		36,00	-	Max face Height in mm
Min face width (in mm, 0 = auto)		25,00	_	Min face width in mm
Max face width (in mm, 0 = auto)		29,00	-	Max face width in mm
Min distance from the eyes (horizontal line)) to the botto	om (in mm, 0 = auto) 25,00	_	Min distance from eyes
Max distance from the eyes to the bottom	(in mm, 0 =	auto) 0,00	-	Max distance from eyes
Distance between the top and the face (in i	mm, 0 = aut	。) 0,00		Distance value in mm
	OK	Cancel		

16. Click **OK** to save your changes.



- 17. The new passport product has been added. In the example below, two new passport products are added:
 - ID Photo_FRANCE
 - Passport Photo_FRANCE





Passport Pricing:

When a new passport product line item is added to the product, a pricing value can be added as well.



- By default, 'All Countries' can have only one pricing value.
- Any new product line can have its own priciong value.

<u>Prices</u>

18. To setup prices an external keyboard is needed (not included with most configurations)



	Confic	auration
Prices		
	export prices	s 💿 import prices
Print Single sided photo card Double sided photo card Calendar	4x4 (Dnp) Per number of pages From Price Service fee add remove	Visible copy prices paste prices
Photobook Print with frame Passport photo	4x6 (Dnp) Per number of pages From Price Service fee add remove	Visible copy prices paste prices
	8x4 (Dnp) Per number of pages From Price Service fee	Visible copy prices paste prices
	🗲 back (Close In service

- **Visible**: White check (ON) means the product is visible to the customer.
- Add Remove: Add or remove a price value. To enable product pricing it is necessary to add at least one price.
- From: Minimum numbers of copies for current price break.
- **Price**: Price for one unit of product (example: price for one print).
- Service Fee: Fixed price for order. In cases of an order with multiple service fees only the maximum service fee will be added to the total.



• Copy Prices/Paste Prices: Function to copy and paste the prices from one product to another.

Note:

For Photobooks and Calendars it is possible to set additional prices based on number of images. For Photobooks it is possible to set also a third additional price based on number of pages.

		import prices	
	From Price Service fee Add remove add remove	From Price Service fee add remove	
Double sided photo card Calendar	8x12 Landscape (Dnp)	Visible copy prices paste price	5
Photobook Print with frame Passport photo	From Price Service fee From Price Service fee 1 15.00 € 4,00 € 1 1,00 € 0,40 € 10 0,00 € 0,00 € 10 0,00 € 0,00 €	e From Price Service fee 1 0,00 € 0,00 €	
	add remove add remove 8x12 Portrait (Dnp) Per product quantity Per number of pages From Price Service fee From Price Service fee From Price Service fee	add remove Visible copy prices paste price Per number of images From Price, Service fee	

Frames

The software is delivered with a number of frames, or borders, already installed. Use this option to add more frames. This feature allows enhanced pictures with graphic elements like borders, logos, and banners. The imported frame file must be:



- A PNG file with a transparent area for the image.
- The same aspect ratio as the print format.
- Minimum resolution of 6x4 frame: 1200x1800 pixels.
- Transparent area of the file may have shade this will be printed on top of the image that is added.
- The PNG files are stored on the system for use with the software.

Creating New Frames

•

- Defining the border: image format type .PNG
 - Define the overall border image size
 - <width>###</width>
 - <height>###</height>
 - Example of 6x4 @ 300 dpi:
 - <width>1800</width><height>1200</height>
 - Define top-left corner of alpha channel
 - <alpha x="###" y="###" width="xxx" height="xxx" rotation="xx" />
 - This is where the image in the border starts, its top-left pixel location
 - Define the width & height of the alpha channel
 - <alpha x="xxx" y="xxx" width="###" height="###" rotation="xx" />
 - This is how wide and tall you want your image in the border to be
 - Define rotation of the alpha channel
 - <alpha x="xxx" y="xxx" width="xxx" height="xxx" rotation="###" /</p>
 - Rotation measured in degrees
 - A value of 15 will rotate the image within the border 15 degrees
- 3:2 ASPECT RATIO 1:1 6:5 5:4 7:5 4:3 2:1 1 1.2 1.25 1.27 1.3 1.4 1.43 1.33 1.5 2 **Multiply Short Side** by: 3.5x5 5x5 8x10 5x7 6x8 4x6 6x9 6x6 Image size in inches: 8x12 8x8 13x18 9x13 15x20 13x13 20x25 10x15 Image size in 15x15 15x23 20x20 20x30 centimeters
- Aspect ratio per print size:

• Example layout design for 4x6" / 10x15cm size:





Attention:

The photo editing software doesn't allow editing existing templates. The frame/border must be created with third party software, like Adobe Photoshop. import the designed borders/frames as an individual files or from a folder.

Note:

To import the designed/created frame/borders, Go to Settings/General/products/Frame/

Template Design Parameters:

- Defining the Template: image format type .JPG
 - (A) Define the overall template image size with the desired design
 - width>###</width>
 - <height>###</height>
 - Example of 8x12 @ 300 dpi:
 - <width>2400</width><height>3600</height>
 - (B) Save the template in .jpg format
- Applying the template in the photo editing software:
 - (C) To import the designed/created frame/borders, Go To:
 - Settings/General/products/Template/
 - For more details, please refer the previous user manual v1.8
- Example of template layout design for 8x12" / 20x30cm size:





Example of Importing a Frame

From the Configuration screen, click the Frames option.

eneral	Products
initial parameters	printer parameters
language	products
photo sources	prices
image editing	themes
end user informations	frames
receipt	
process confirmation	

19. Click on Import Files.



- 20. The file browser opens. Browse to and select the file(s) to be used as frames.
- 21. Click Open to import the file(s)
- 22. Click **Close** to close frames import window
- 23. Close the program and restart the software.
- 24. The new frames are now available on all frame products.


<u>Themes</u>

Themes (for creative products) allow you to import backgrounds that are used to create personalized products. A theme is a group of backgrounds. Backgrounds can be imported from a file or generated choosing color from a palette.

The file with a background must be:

- jpg image
- Square size ratio is recommended to easily crop to the correct print aspect ratio.

For each theme it is possible to set a default font for text and a default size for the border to be placed around inserted images (if the default border size is zero, no border is added to images). For each backgro und it is possible to select default color for text and default color for image border.

Adding New Themes from Images

1. From the Configuration page, click the **Themes** option.

initial parameters	printer parameters
language	products
photo sources	prices
image editing	themes
end user informations	frames
receipt	
process confirmation	

2. Click New.

Default themes	
	new 🖉 edit 🏛 delete 🕟 new page 🅥 un 🕒 down 🌚 cut 🕲 paste
Bainbow	
Flowers	
Black	
White	
Kaleidos	
	Close
	🕞 back 🜔 in service

- 3. Enter a name for the theme.
- 4. Click the **Backgrounds** button.



Default themes inew category \bigoplus new \bigotimes edit (Rainbow Flowers Black White Kaleidos	Thomos Twee
	🕞 back 🕑 in service

5. Click Image from .jpg file.

Default themes	Theme	
Backgrounds Backgrounds for this theme Default backg	Choose the object to create Image from .pg file Plain color OK Cancel	Jown Cut paste import
	OK Cancel	Close
	Duck Din survice	

- 6. Enter the Image Name.
- 7. Click on **Background Image** and import your images.

Default themes Backgrounds Backgrounds for this theme Default background new category \bigoplus new $$ edit $$ defe	Image from .jpg file Image territor territe
	🕞 back 🕞 in survice

8. Select the **text color** and the **border color**.



	- Image from ing file
Default themes	Name Sand
Backgrounds Backgrounds for this theme Default background Pedit () dele	Beciground mage () up () down () cut () paste () import Close OK Cancel

- 9. Click **OK** to save your changes.
- 10. Close any other open windows and restart the software. The new theme is added to available themes.

Rainbow	Flowers	Black		
White	Kaleidos Materials			
🕞 back 🛞 cancel				



11. Diagnostics

-SnapLab + 1.1.18.5 Main Panel				
Settings	Pictures	Stats	Diagnostics	Diagnostics orders in process receipt printer test export logs
				printer status
				update license
				check for updates
Computer reboot			In service	teamviewer
	Din	service		

Team Viewer

When the system requires remote support, connect with an internet connection and provide the Team Viewer ID to the support person as needed.

- 1. From the Main Panel, select the **Diagnostics** button.
- 2. Select the **Teamviewer** option.
- 3. When prompted, enter the password: dnppiesupport (in small letters with no space)
- 4. Wait for the DNP-PIE Remote Support window to appear.



Printer Status

- 1. From the Main Panel, select the **Diagnostics** button.
- 2. Select the Printer Status option.

Printers status					
Model	Serial number	Media size	Remaining prints	Status	Firmware
DS620	DS6X55004409	6x8	100	IDLE	DS620 01.41
DS820	CS6070102	8x12	18	IDLE	DS820 01.05
					Close

3. Use the information on this screen to identify your printers and the current status of each printer.



Orders in Process

To list the orders which are in process and therefore are not yet printable. All orders with any error condition are listed here.

- 1. From the Main Panel, select the **Diagnostics** button.
- 2. Select the **Orders in Process** option.
- 3. Following options are available:
- 4. Show Error: Displays details about any error conditions for the selected order.
- 5. Delete All Orders in Error: All orders with an error condition will be permanently deleted.

Receipt Printer Test

- 1. From the Main Panel, select the **Diagnostics** button
- 2. Select the Receipt Printer Test option.
- 3. A test print is sent to your receipt printer.

Export Logs

To create a compressed folder containing log files, useful to report eventual problems with the system.

- 1. From the Main Panel, select the **Diagnostics** button.
- 2. Select the **Export Logs** button.
- 3. Logs are exported to the specified loction.

Software Update

By clicking on the button **Check for Updates** the system will search for an update. If there is an update, the software will prompt a message to quit and launch the update process.



1. When there is an update, the following message is shown.



- 2. Click **OK** to continue and click **Restart Application** to restart the software and begin the update process.
- 3. If the software update has already been installed, the following message is displayed. Press **OK** to continue.

You have already installed the latest version.

4. If there is no internet connection, the following message appears. Press OK to continue.



Updating the Software without an Internect Connection

It is possible to use another way to update the software; by downloading the installer from: <u>http://www.dnpphoto.com/downloads/</u> and selecting the product name.

Attention:

The instruction below is only for the Snap Lab system.

- 5. Exit all applications.
- 6. After downloading the software, copy and extract the zip file on the desktop of the system.
- 7. Open the folder and access the installer file. Double-click on the installer and follow the installation instructions.

Welcome to the DS-Tmini Wizard	Setup	icense Agreement Please read the following imp	portant information before continuing.
This will install DS-Tmini (1.0.26.5) on your comp It is recommended that you close all other applic	outer.	Please read the following Lice agreement before continuing	ense Agreement. You must accept the terms of this 9 with the installation.
Click Next to continue, or Cancel to exit Setup.		Fit Engineering s.r.l. End-Us between you (either an Indi the Fit Engineering s.r.l. sof associated software compor electronic documentation (°) otherwise using the SOFTW of this EULA. This license ag the program between you a and it supersedes any prior the parties. If you do not ag the SOFTWARE PRODUCT. I accept the agreement I do not accept the agree	er License Agreement ("EULA") is a legal agreement vidual or a single entity) and Fit Engineering s.r.l. for tware product(s) identified above which may include nents, media, printed materials, and "online" or SOFTWARE PRODUCT"). By installing, copying, or ARE PRODUCT, you agree to be bound by the terms reement represents the entire agreement concerning and Fit gs.r.l., (referred to as "licenser"), propos gree to 2 of this EULA, do not install or use
Next >	Cancel		< Back Next > Cancel
Setup - DS-Tmini	×		Setup - DS-Tmini 🛛 🗕 🗆 🗙
mportant information before continuing. License Agreement. You must ac ing with the installation. User License Agreement ("EULA" Liser License Agreement ("EULA" Software product(s) identified above which may i sonents, media, printed materials, and "online" on ("SOFTWARE PRODUCT"). By installing, copying WARE PRODUCT, you agree to be bound by the agreement represents the entire agreement con or proposal, representation, or understanding be agree to the terms of this EULA, do not install or r.	of this ement ^ r.r.l. for r between r, or teterms set"), etween r use		Completing the DS-Tmini Setup Wizard Setup has finished installing DS-Tmini on your computer. The application may be launched by selecting the installed icons. Click Finish to exit Setup.
< t ack Next >	Cancel		Finish
	Welcome to the DS-Tmini Wizard This will install DS-Tmini (1.0.26.5) on your comp It is recommended that you close all other applic continuing. Click Next to continue, or Cancel to exit Setup. Lext > Setup - DS-Tmini mportant information before continuing. Setup - DS-Tmini mportant information before continuing. Ser License Agreement. You must ac ng with the installation. Jser License Agreement ("EULA Jser License Agreement ("EULA Software product(s) identified above which may orents, media, printed materials, and "online" of "SOFTWARE PRODUCT"). By installing, copying WARE PRODUCT, you agree to be bound by the agreement represents the entire agreement cor and Fit Engineering s.r.l., (referred to as "licen r proposal, representation, or understanding be agree to the terms of this EULA, do not instal of the ement	Welcome to the DS-Tmini Setup Wizard This will install DS-Tmini (1.0.26.5) on your computer. It is recommended that you dose all other applications before continuing. Click Next to continue, or Cancel to exit Setup. I Next> Cancel Setup - DS-Tmini mortant information before continuing. Setup - DS-Tmini Ser License Agreement. You must at ng with the installation. Jar License Agreement ("EULA" agreement dividual or a single entity) and Fit Engineering s.r.l., (referred to as "icenser"), or proposal, representation, or understanding between agree to the terms of this EULA, do not install or use to the terms of this EULA to the terms of th	Welcome to the DS-Tmini Setup Wizard Hesse read the following inter This will instal DS-Tmini (1.0.26.5) on your computer. Please read the following Lite agreement before continuing. Click Next to continue, or Cancel to exit Setup. Please read the following Lite agreement before continuing. Iter commended that you dose all other applications before continuing. Please read the following Lite agreement before continuing. Iter commended that you dose all other applications before continuing. Iter Commended the filt Engineering s.r.l. End Agreement before eny ou (either an indi- between you is setup s.r.l. sod associated software compo- ale to the setup with the installation. Iter commended that you dose all other applications before continuing. Iter Commended the filt Engineering s.r.l. End Agreement is compared between you at and it supersides any prior the parties. If you do not a and it supersides any prior the parties. If you do not a and it supersides any prior the software compo- ing with the installation. Inserted the filt Engineering s.r.l. and a greement dividual or a single entity) and Fit Engineering s.r.l. for forware product(s) identified above which may indiced or (SOFTWARE PRODUCT). By installing, copying, or Your proposal, representation, or understanding between agree to the terms of this EULA, do not install or use the ement Ite field inter is setting the stallation. Ite field intervient is s.r.l. (Field is a Site Site Site Site Site Site Site Site

8. Click **Finish** (see image number above 4) and restart the system.

Attention:

Do not interrupt the installation process during the installation!



12. Statistics



- 1. Access the statistics screen from the Main Panel.
- 2. Press the **Stats** button.
- 3. Use this section to view production stats for the kiosk.
- 4. It is possible to filter the information visible on the screen.
- 5. It is possible to export the data in an Excel file for further analysis.



13. Change Mode: Photo Editing Software vs Party Print

By default the system is configured to Photo Editing Software, so to change the system configuration to Party Print the configuration mode must be changed.

If you have a PartyPrint with the Snap Lab, please connect the PartyPrint license dongle to the Snap Lab and change the Wi-Fi Router and turn it on.

Change to Party Print Mode

- 1. Exit the software.
- 2. Enter into Main Panel by touching in sequence to the lower left and right corners of the monitor.



3. Click the Quit Application button.



- 4. Please wait for a few seconds.
- 5. The system will show up another application called LaunchPad.
- 6. To change the mode, click the **Advanced** button.





7. Type the password **1600**.



- 8. Click the **Mode** button quickly.
- 9. The advance control will disapper in 3-5 seconds.

	D Photo I	NP maging	
Restart Applications	Restart Computer	Shutdown Computer	Advanced
Language	Мо	de	Exit

10. By clicking on the Mode button the software will display 2 options:

- Current Configuration: Photo Editing Software (Snap Lab);
- Available Configuration: Party Print.

Note:

The current configuration won't be accessible; as it's the actual confuguration. This will be respected in any mode (Photo Editing Software vs Party Print).

11. Click on Available Configuration then Party Print and follow the instructions.

Choose your configuration?			
Current Configuration	Available configuration		
SnapLab*	PartyPrint		
6	a de la constante de		

12. Please follow the instruction carefully before clicking on the **OK** button.



13. Connect the PartyPrint dongle and change the Wi-Fi Router.



- 14. Click on **OK** and the system will restart in a few seconds automatically.
- 15. The system will launch the application Party Print Utility.
- 16. Please refer Party Print Utility user manual for more details.

artyPrint Utilit	Change Language English Apply View Help Page
Print: Size &	Period Image: Session & Archive Customize Party Print Mobile Interface Template
Output Print	Size & Border
Print Size Borders	35.55 466 507 668 609 465 View Apply
Printing Per	iod
Date	Off
Start:	Select a date 🔝 HH24 mm ss
End:	Select a date s HH24 mm ss
	Save & Launch Party Print V 1.8

17. PartyPrint Utility provides same functions as PartyPrint.

Note:

PartyPrint Utility requires license dongle to work with the software. If not the system will display an error message.



- 18. After verifying the required configuration for PartyPrint, please click on **Save & Launch Party Print** button to start the PartyPrint software.
- 19. The below screen is the main page of the Party Print software.





Note:

For more details on PartyPrint, please refer the user manual of PartyPrint.

Launching the Same Mode Again

Simply click on the 'Restart Application' button to re-launch the existing configuration software.



Note:

If the system current configuration is PartyPrint, then the system will launch PartyPrint Utility. Simply click on Save & Launch Party Print button (the steps above).

Change to Photo Editing Software Mode

- 20. Exit from PartyPrint
- 21. To access the Administrative Options, touch and hold the PartyPrint Icon in the top left corner.

PartyPrint

- 22. When the keypad appears, enter the password (default is **4103**) and press OK. From here you can access the following:
 - **Exit Application**: Exit the application, and return to the desktop.
 - **Cancel**: Exit the Administrative Options menu, and return to the main screen.
- 23. Please wait for a few seconds.
- 24. The system will show up another application called LaunchPad.
- 25. To change the mode, click the Advanced button.

	-	
_	-	-
4	5	6
7	8	9
	0	Back





26. Type the password 1600.



- 27. Click the Mode button quickly.
- 28. The advance control will disapper in 3-5 seconds.



- 29. By clicking on the Mode button the software will display 2 options:
 - Current Configuration: Photo Editing Software (Snap Lab);
 - Available Configuration: Party Print.

Note:

The current configuration won't be accessible; as it's the actual confuguration. This will be respected in any mode (Photo Editing Software vs Party Print).

30. Click on Available Configuration, Snap Lab button control & follow the instructions.



Choose your configuration?				
Current Configuration	Available configuration			
SnapLab ⁺	PartyPrint			
	Exit			
inapLab+ requires the wireless name 'OPhotoPrints' (Zero) for th	ne mobile app 'PhotoPrints'			
Please Turn 'On' the 'OPhotoPrints' router before cor outer is not Turned 'ON' then the configuration can	nnecting. Connect the router to the DS-Tmini, if the not be work properly			
Press 'Ok' to restart your system. The system will restart with the	e Mode SnapLab+			
Press 'Cancel' to close this Window				
ок	Cancel			

Note:

Please follow the instruction carefully before clicking on the Ok button. Remove the PartyPrint dongle and change the Wi-Fi Router.

- 31. Click the **OK** button and the system will re-start in few seconds automatically.
- 32. The system will launch the software 'Photo Editing Software'.



33. Touch the screen to start working with the system.



14. Printers configuration support

System Configurations

For better usage & performance of the system, we recommend using any one of the following configurations:

Configuration Type 1	Configuration Type 3		Configuration Type 5
DS620	DS620 with DS820		
		-	2 DS620 1 DS820 or DS80
Configuration Type 2	Configuration Type 4		2 03020, 1 03820 01 0380
DS620 with DS80DX	DS620 with DS80		
Configuration Type 6	Configuration Type 7		
DS620 with RX1 or RX1HS	DS620 with DS40		

Caution: Trying different configurations apart from the above are not supported by DNP

1. Please do not use same media type, For ex: 6x8 media on both DS620/DS40

2. Please do not connect two different printers of the same media type DS820 & DS80

3. Please do not connect DS80DX along with DS80, instead of DS80 please use DS820 for better performance & various print sizes.

4. Please do not connect printer DS620 w 6x8 media and printer RX1/RX1HS with 6x8 media.

Note:

For product matrix & supported media type per printer; verify the below table. For more information please contact our support team at: <u>Support@dnpphoto.com</u>



Printer Matrix

SL+ Product Matrix in Centimeter:

Product	Size	Printer W Media
Print Products: Simplex		
Simple Prints	9 x 13	DS 620 / RX1
Simple Prints	10 x 10 (Trim)	DS 620 / RX1
Simple Prints	10 x 15	DS 620 / RX1
Simple Prints	(10 x 15)2	DS 620 / RX1 w 15x20 Media
Simple Prints	(11 x 15)2	DS 620 w 6x9 Media
Simple Prints	13 x 13	DS 620/RX1
Simple Prints	13 x 18	DS 620 /RX1/DS 820*
Simple Prints	15 x 15	DS 620/RX1
Simple Prints	15 x 20	DS 620 /RX1/ DS 820
Simple Prints	15 x 23	DS 620 / DS 820*
Simple Prints	20 x 20	DS80 / DS 80 DX / DS 820
Simple Prints	20 x 25	DS80 / DS 80 DX / DS 820
Simple Prints	20 x 30	DS80 / DS 80 DX / DS 820

Print Products : Panoramic				
Panoramic Prints	15x35	DS 620 w 15x20 Media		
Panoramic Prints	15x50	DS 620 w 15x20 Media		
Panoramic Prints	20x45	DS 820 w 20x25		
Panoramic Prints	20x65	DS 820 w 20x25		
Panoramic Prints	20x55	DS 820 w 20x30		
Panoramic Prints	20x80	DS 820 w 20x30		

Product	Size	Printer W Media
Print Products : Calendars		
Calendar 1 Page Simplex	20 x 25	DS80 DX / DS 80 / DS 820
Calendar 2 Pages Duplex	20 x 25	DS80 DX
Calendar 13 Pages Duplex	20 x 25	DS80 DX
Calendar 13 Pages Simplex	20 x 25	DS80 DX / DS 80 / DS 820
Calendar 1 Page Simplex	20 x 30	DS80 DX / DS 80 / DS 820
Calendar 2 Pages Duplex	20 x 30	DS80 DX
Calendar 13 Pages Duplex	20 x 30	DS80 DX
Calendar 13 Pages Simplex	20 x 30	DS80 DX / DS 80 / DS 820
Calendar Single Page	15 x 20	DS 620 /RX1/ DS 820
Calendar 13 Pages Simplex	15 x 20	DS 820 / DS 620
Calendar 13 Pages Simplex	10x20	DS 80 / DS 820
Calendar Single Page	13 x 18	DS 620 /RX1/ DS 820*
Calendar Single Page	15 x 20	DS 620 /RX1/ DS 820

Print Products: Double Sided			
Double Sided Prints	10 x 20	DS80 DX	
Double Sided Prints	15 x 20	DS80 DX	
Double Sided Prints	20 x 20	DS80 DX	
Double Sided Prints	20 x 25	DS80 DX	
Double Sided Prints	20 x 30	DS80 DX	

Print Products : Frames / Borders				
Simple Prints with Frame	9 x 13	DS 620 / RX1		
Simple Prints with Frame	10 x 10 (Trim)	DS 620 / RX1		
Simple Prints with Frame	10 x 15	DS 620 / RX1		
Simple Prints with Frame	13 x 13	DS 620		
Simple Prints with Frame	13 x 18	DS 620 / RX1		
Simple Prints with Frame	15 x 15	DS 620 /RX1/ DS 820		
Simple Prints with Frame	15 x 20	DS 620 /RX1/ DS 820		
Simple Prints with Frame	15 x 23	DS 620 w 15x23 Media		
Simple Prints with Frame	20 x 20	DS80 / DS 80 DX / DS 820		
Simple Prints with Frame	20 x 25	DS80 / DS 80 DX / DS 820		
Simple Prints with Frame	20 x 30	DS80 / DS 80 DX / DS 820		

Print Products : PhotoBooks				
Photo Book	10 x 10	DS80 DX (White Trim)		
Photo Book H/V	10 x 15	DS80 DX (White Trim)		
Photo Book H/V	10 x 20	DS80 DX (White Trim)		
Photo Book H/V	15 x 20	DS80 DX		
Photo Book	20 x 20	DS80 DX		
Photo Book H/V	20 x 25	DS80 DX		
Photo Book H/V	20 x 30	DS80 DX		

Print Products : Greeting Cards			
Greeting Card Simplex	10 x 20	DS80 / DS 80 DX / DS 820	
Greeting Card Simplex	15 x 20	DS80 / DS 80 DX / DS 820	
Greeting Card Double Side	10 x 20	DS80 DX	
Greeting Card Double Side	15 x 20	DS80 DX	

Print Products : ID Photo / Passport			
ID Photo	10 x 15	DS 620 / RX1	

* : White space on the right side of the print

Printer with supported Mee	dia	Printer with	n supported Media
DS 620	10x15, 13 x 18		9x13
	15 x 20	DV1	10x15
	15 x 23	KAI	13x18
DS 820	20 x 25(Standard, Premium)		15x20
	20 x 30(Standard, Premium)	DC 90	20 x 25
RX1 HS	9x13	D2 80	20 x 30
	10x15		20 x 25 Duplex Media
	13x18	DS 80 DX	20 x 30 Duplex Media
	15x20		

Note: 15x23 simplex calendar with 15x23 media only

Caution: Please do not mix DS 820 media with DS 80 vice versa; RX1 HS printer detects HS media only where RX1 can detect both HS/Standard

Duinton W/ Modia

SL+ Product Matrix in Inches:

Product	Size	Printer W Media	Product	Size	
Print Products: Simplex		Print Products : Calendars	0.120		
Simple Prints	3.5 x 5	DS 620 / RX1	Calendar 1 Page Simplex	8x10	DS
Simple Prints	4 x 4 (Trim)	DS 620 / RX1	Calendar 2 Pages Duplex	8x10	DS
Simple Prints	4 x 6	DS 620 / RX1	Calendar 13 Pages Duplex	8x10	DS
Simple Prints	(4 x 6)2	DS 620 / RX1 w 6x8 Media	Calendar 13 Pages Simplex	8x10	DS
Simple Prints	(4.5 x 6)2	DS 620 w 6x9 Media	Calendar 1 Page Simplex	8x12	DS
Simple Prints	5 x 5	DS 620/RX1	Calendar 2 Pages Duplex	8x12	DS
Simple Prints	5 x 7	DS 620/RX1	Calendar 13 Pages Duplex	8x12	DS
Simple Prints	6 x 6	DS 620 /RX1	Calendar 13 Pages Simplex	8x12	DS
Simple Prints	6 x 8	DS 620 / DS 820*	Calendar Single Page	6x8	DS
Simple Prints	6 x 9	DS 620 / DS 820*	Calendar 13 Pages Simplex	6x8	DS
Simple Prints	8 x 8	DS80 / DS 80 DX / DS 820	Calendar 13 Pages Simplex	4x8	DS
Simple Prints	8 x 10	DS80 / DS 80 DX / DS 820	Calendar Single Page	5x7	DS
Simple Prints	8 x 12	DS80 / DS 80 DX / DS 820	Calendar Single Page	4x6	DS

	Product	512e			
	Print Products : Calendars				
ſ	Calendar 1 Page Simplex	8x10	DS80 DX / DS 80 / DS 820		
	Calendar 2 Pages Duplex	8x10	DS80 DX		
	Calendar 13 Pages Duplex	8x10	DS80 DX		
	Calendar 13 Pages Simplex	8x10	DS80 DX / DS 80 / DS 820		
	Calendar 1 Page Simplex	8x12	DS80 DX / DS 80 / DS 820		
	Calendar 2 Pages Duplex	8x12	DS80 DX		
	Calendar 13 Pages Duplex	8x12	DS80 DX		
	Calendar 13 Pages Simplex	8x12	DS80 DX / DS 80 / DS 820		
	Calendar Single Page	6x8	DS 620 /RX1/ DS 820		
	Calendar 13 Pages Simplex	6x8	DS 820 / DS 620		
	Calendar 13 Pages Simplex	4x8	DS 80 / DS 820		
	Calendar Single Page	5x7	DS 620 /RX1/ DS 820*		
	Calendar Single Page	4x6	DS 620 /RX1/ DS 820		

Print Products : Panoramic				
Panoramic Prints	6x14	DS 620 w 6x8 Media		
Panoramic Prints	6x20	DS 620 w 6x8 Media		
Panoramic Prints	8x18	DS 820 w 8x10		
Panoramic Prints	8x26	DS 820 w 8x10		
Panoramic Prints	8x22	DS 820 w 8x12		
Panoramic Prints	8x32	DS 820 w 8x12		

Print Products: Double Sided			
Double Sided Prints	4 x 8	DS80 DX	
Double Sided Prints	6 x 8	DS80 DX	
Double Sided Prints	8 x 8	DS80 DX	
Double Sided Prints	8 x 10	DS80 DX	
Double Sided Prints	8 x 12	DS80 DX	

Print Products : Frames / Borders				
Simple Prints with Frame	3.5 x 5	DS 620 / RX1		
Simple Prints with Frame	4 x 4 (Trim)	DS 620		
Simple Prints with Frame	4 x 6	DS 620 / RX1		
Simple Prints with Frame	5 x 5	DS 620		
Simple Prints with Frame	5 x 7	DS 620 / RX1		
Simple Prints with Frame	6 x 6	DS 620 / RX1		
Simple Prints with Frame	6 x 8	DS 620 / RX1		
Simple Prints with Frame	6 x 9	DS 620		
Simple Prints with Frame	8 x 8	DS80 / DS 80 DX		
Simple Prints with Frame	8 x 10	DS80 / DS 80 DX		
Simple Prints with Frame	8 x 12	DS80 / DS 80 DX		

Print Products : PhotoBooks			
Photo Book	4x4	DS80 DX (White Trim)	
Photo Book H/V	4 x 6	DS80 DX (White Trim)	
Photo Book H/V	4 x 8	DS80 DX (White Trim)	
Photo Book H/V	8 x 6	DS80 DX	
Photo Book	8 x 8	DS80 DX	
Photo Book H/V	8 x 10	DS80 DX	
Photo Book	8 x 12	DS80 DX	

Print Products : Greeting Cards				
Greeting Card Simplex	4x8	DS80 / DS 80 DX / DS 820		
Greeting Card Simplex	4x8	DS80 / DS 80 DX / DS 820		
Greeting Card Double Side	6x8	DS80 DX		
Greeting Card Double Side	6x8	DS80 DX		

Print Products : ID Photo / Passport			
ID Photo	4x6	DS 620 / RX1	

: White space on the right side of the print

Printer w	vith supported Media	Printer	with supported Media
	4x6, 5x7		3.5x5
DS 620	6x8	51/4	4x6
	6x9	RXI	5x7
DC 830	8x10 (Standard, Premium)		6x8
DS 820	8x12 (Standard, Premium)	DC 00	8x10
	3.5x5	DS 80	8x12
RX1 HS	4x6		8x10 Duplex Media
	5x7	D3 80 DA	8x12 Duplex Media
	6x8		

*

Note: 6x9 simplex calendar with 6x9 media only

Caution: Please do not mix DS 820 media with DS 80 vice versa; RX1 HS printer detects HS media only where RX1 can detect both HS/Standard



DS820 Printer Support



DNP is pleased to introduce brand new 8" inch printer with various features.

Some Key Features:

- More print formats/sizes
- New photo finishes: Luster, Fine Matte along with Glossy & Matte
- Rewinding function*
- Standby mode for less power consumption
- Supports standard digital media & High Quality media

*Rewind function available only in certain global regions.

Attention:

DS820 printer detects both Standard & High Quality media.

Please refer Product Matrix for supported products/print sizes for DS820

For more details on the DS820 printer, please refer to our website: http://www.dnpphoto.com/Printers/DS820A

DS820 High Quality Media Support

- DS820 brings the high definition printing using High Quality media.
- The operator can activate the 'High Definition' mode for HQ media.
 - Go to, Admin, Settings/products/printer parameters/High Density print on supported printers/
 - ON/OFF (default value : NO)
- The HD mode works on both 300x300 dpi & 300x600 dpi (recommend using 300x600 dpi)

0	Go to, Admin, Settings/products/printer parameters/Resolution/	Resolution
0	ON/OFF (default value : 300X300 dpi)	300 x 300 dpi

Note:

The software detects HQ media and activated HD mode automatically

Do not change the media type from Standard to HQ or vice versa in the middle of a print job, in case of a media over



RX1HS printer support

The Photo Editing Software supports new RX1HS printer (HS: High Speed 20% faster than RX1):



RX1HS printer detects only HS media, where RX1 printer detects both standard & HS media. Please refer "Product Matrix" for supported product/print sizes for RX1HS. The products & print sizes are same for both RX1 & RX1HS printer. For more details on the RX1 HS printer, please refer to our website: <u>http://www.dnpphoto.com/Printers/DS-RX1HS</u>



15. DNP DS-Printer Firmware Upgrade

From the PES (photo Editing Software) version 1.4.31.7, the firmware upgrade for DNP Printers made it easy; i.e. the software will flash the firmware automatically when a DNP printer is connected with the system (Snap Lab Hardware).

Firmware Upgrade Process - Automatic:

Let us consider that the new software is properly installed in the system and the system has been restarted successfully.

- 1. The system will detect the connected the DS620 printer to check the firmware version.
- 2. If the firmware version is less than v1.41 on DS620, then update process will start automatically.
- 3. Please wait until the below process have been completed:

	Importing initial parameters
Firmware up p	grade is in progress. Please do not disconnect the rinters before the end of the operation.

Note:

The printer produces multiple beeps & flashing LEDS. At the end of the successful firmware upgrade, the printer will put back to green color LED.

	14/-11	
	Wait	

4. Finally the system will display the screen saver of the software.

Attention:

Please do not turn of the printer while the software is flashing the firmware. The firmware update is for DS620 and DS820 only; not for any other DNP DS Printers. The software won't upgrade firmware on multiple printers (DS620 / DS820) at the same time; always one printer at a time. For **DS620 v: 01.41; DS820 v: 01.05** is the correct version for this software release.

5. To confirm the printer firmware upgrade: Settings/Diagnostics/Printer Status:

Printers status						
Model	Serial number	Media size	Remaining prints	Status	Firmware	
DS620	DS6X55004409	6x8	100	IDLE	DS620 01.41	
DS820	CS6070102	8x12	18	IDLE	DS820 01.05	
					Close	

Firmware Upgrade Process - Manual:

The PES allows manual firmware upgrade for DNP DS Printers, Settings/Diagnostics/update firmware/:

- 1. Please make sure the DNP Printer (DS620 or DS820) is connected & turned ON.
- 2. Click on the button **Update Firmware**.
- 3. Please click on **OK** of the confirmation message.

4. Wait for the software finishes the firmware upgrade process.



Attention:

Please do not turn of the printer while the software is flashing the firmware. The firmware update is for DS620 and DS820 only; not for any other DNP DS Printers. The software won't upgrade firmware on multiple printers (DS620/DS820) at the same time; always one printer at a time. For **DS620 v: 01.41; DS820 v: 01.05** is the correct version for this software release.



16. DS620 Printer 6x9 Firmware Update

Some DS-620 printers may not be updated with 6x9 inch firmware. We apologize for the inconvenience.

- 5. Remove the 6x9 media and place the 6x8 media.
- 6. The update cannot be performed with 6x9 media inside the printer.
- 7. Exit from Photo Editing Software or from Party Print.
- 8. Exit from Launchpad software.
- 9. To change the mode, click on the **advanced** button.



10. Type the password **1600**.

Enter Password		Password : <u>1600</u>
1 4 5 6 7 8 9		
Cancel OK	Ur Advanced	

- 11. Please click on the **Mode** button quickly.
- 12. The advance control will disapper in 3-5 seconds.

Restart Applications	Restart Computer		Shutdown Computer	Advanc	ed
Language		Mode		Exit	

- 13. Click on Exit button (see the top screen-shot).
- 14. Now the system will display the Desktop.

Do not delete any icon/files from the desktop. Deleting any icon/files, the system and Photo Editing Software may not function properly.

15. Open the folder 'DS620_6x9_FW_Driver_Update_With Procedure'.





🚹 l 💽 🚹 = l	VersionUpTool				
File Home Share	View				
Copy Paste Copy pat Clipboard	th ortcut Nove Copy to * to * Organize	New item • New folder New	Properties	Select all Select none Invert selection	
(→ ↑) → DS620_6x9_FW_Driver_Update_With Procedure → DS620_6x9_FW_Driver_Update → 1_FW_Update_6x9 → VersionUpTool					
 ★ Favorites ■ Desktop ➡ Downloads ➡ Recent places 	Name DP-DS620 0110 Win64 VersionUpTool_DP-DS620_0110_EN	Date modified 28/04/2015 06:57 31/07/2015 16:12	Type Application PDF File	Size 876 KB 361 KB	

- 16. Go to the folder **VersionUpTool**.
- 17. Double click on the file **DP-DS620_0110_Win64**.
- 18. Select Printer DP-DS620
- 19. Click on Start then click the End button when it is prompted.

	R DP-DS620 Version Up Tool	NDP-DS620 Version Up Tool
	Now Firmware Ver DS620 00.33 Printer Firm Ver DS620 00.33	New Firmware Ver DS620 00.33 Printer Firm Ver
	CWD Vor 300 DS520_300_0012CWD Sum 2988 CWD Vor 600 DS520_600_0012CWD Sum FCC9 CWD Vor 500 DS520_610_0012CWD Sum 5444 ** Firmwore Update** Push START button.	CWD Ver 300 DS620_300_0012CWD Sum 2888 CWD Ver 500 DS620_500_0012CWD Sum FCC9 CWD Ver 5300 DS620_510_0012CWD Sum 5444 ** Printer error ** Push END botton. ************************************
Printer setting	Status Transmitting data is prepared.	Status Transmitting data is prepared.
Please select printer.	The printer changes to the rewrite mode. Firmware is transmitted. Firmware is written in flash ROM. CWD data is transmitted and written.	The printer changes to the rewrite mode. Firmware is transmitted. Firmware is written in flash ROM. CWD data is transmitted and written.

- 20. If the printer is not connected then the software will display the below message.
- 21. Please check the printer USB is properly connected with the Snap Lab system.



- 22. For more details on 6x9 FW update please refer to VersionUpTool_DP-DS620_0110_ENG.pdf.
- 23. By default the system has 64 bit FW ugrade executable file because the windows OS is 64 bit.



17. Troubleshooting

Contacting Technical Support

For any technical issue(s) and/or question(s), please contact the support team at:

support@dnpphoto.com

Issue with Wireless Transfer via 'PhotoPrints' App

Incorrect Kiosk ID and Password:

If the screen suggests the following options kiosk for wireless transmission of photos, there is a problem with your PhotoPrints router:

Incorrect IP Address



The router must be connected to Snap Lab and turned ON before starting (turning ON) system

Correct IP Address

5. Select your kiosk: Kiosk ID: Kiosk 99 Password: 99

Local Immediate Print Product is No Longer Available

If you are using DNP printers, the software automatically hides the products which can not be processed. Make sure the printer is powered on, with available media, connected to the Snap Lab and ready to print.